Integrated Camera Interface Specifications

Supplement for Web Control

Target Models

HE40 series

AW-HE70/AW-HE40/AW-HE65 (Ver1.32 and later)

AW-HE48/AW-HE58

AW-HE35/AW-HE38

AW-HN38/AW-HN40/AW-HN65/AW-HN70

UE70 series

AW-UE70

(Ver1.04 and later)

AW-UN70

AW-UE65/AW-UE63

HE42 series

AW-HE42/AW-HE75/AW-HE68

Second Edition

Panasonic Corporation

Change History

December 21, 2015 Initial Release

September 17, 2019 Second Edition Release

(Correction of mistakes, addition of models, addition of functions)

Table of Contents

Change History	1
1. Introduction	4
2. CGI List for Video Transmission	5
2.1. Transmission User Management	5
2.2. Device Information Acquisition	8
2.3. Camera-specific Information (Capability) Acquisition	11
2.4. JPEG-based Image Transmission	
2.5. Image Transmission Sequence based on MJPEG	19
2.6. Image Transmission Sequence based on JPEG Image 1 shot	20
2.7. H264/AUDIO-based Image Transmission	21
2.8. Unicast Image Transmission Sequence based on H264	23
3. CGI List for Camera Control	24
3.1. Pan/Tilt/Zoom	24
4. CGI List for Various Settings	26
4.1. Basic Settings	26
4.2 Clock Settings	27
4.3. Video over IP Settings	28
4.4. Audio Settings	38
4.5. Multi-screen Settings	39
4.6. Priority Stream Settings	40
4.7. Network Settings	41
4.8. UPnP Settings	44
4.9. Restarting	44
5. CGI List for Acquisition of Different Types of Information	45
5.1. Basic Settings Information Acquisition	45
5.2. NTP Settings Information Acquisition	45
5.3. Clock Settings Information Acquisition	46
5.4. Priority Mode Acquisition	46
5.5. VideoOverIP Screen Information Acquisition	47
5.6. Audio Settings Information Acquisition	49
5.7. Multi-screen Settings Information Acquisition	49
5.8. Host Authentication Settings Information Acquisition	50
5.9. Priority Stream Settings Information Acquisition	50
5.10. Network Settings Information Acquisition	51
5.11. UPnP Settings Information Acquisition	51
5.12. System Log Information Acquisition	52
5.13. Camera Status Acquisition	53
5.14. UPnP Execution Results Acquisition	54
5.15. Preset Position Information Acquisition	54
5.16. Other Setting Values Acquisition	55
6. CGI List for HTTPS Control	
6.1. Setting Information and Acquiring Certification	
6.2. Information Acquisition	
7. CGI List for FTP Control	
7.1. FTP Server Settings	
7.2. FTP Server Transfer Instruction	

7.3. FTP Server Information Acquisition	64
7.4. FTP Server Progress Confirmation	64
7.5. FTP Control Sequence	
7.6. About Folder Settings at the FTP Server Side	66
8. CGI List for Recording/Playback Control on SD Card	67
8.1. Video Recording Mode Settings	67
8.2. Video Recording Mode Acquisition	68
8.3. Video Recording Start/End Control	
8.4. SD Card Format (Initialization) Control	
8.5. SD Card Format (Initialization) Progress Confirmation	
8.6. MP4 File List Search	
8.7. MP4 File Playback Control	
8.8. MP4 File Playback Sequence	
8.9. MP4 File Deletion	
8.10. Acquiring Information of MP4 File being Played Back	
8.11. MP4 File Download Control	
8.12. MP4 File Download Sequence	
8.13. Still picture image save	
8.14. Still picture image load / delete / find	
9. Acquiring the List of Setting Values	
10. About Control Based on RTSP	
10.1. About the URLs for an RTSP Request	
10.2. About the rtsp Methods	
11. About Acquisition of Stream from RTSP	
11.1. UDP Unicast	
11.2. UDP Multicast	
11.3. TCP Unicast	
11.4 About the rtpmap Attribute	
12. About Control Based on RTCP	
13. About RTP/Data Format	
13.1. RTP Header Format	
13.2. Relationship with H.264/ES Data	
13.3. H.264 Syntax	
13.4 Audio Data Format	101

1. Introduction

This manual describes the specifications for video transmission and network application operation when a remote camera is operated via the network. For details on the general camera operations of the remote camera, see the separate volume "HD Integrated Camera Interface Specifications".

Panasonic shall not take any responsibility of damages caused as a result of the use of this information. This information may be changed without prior notice due to upgrade of product version in future. The usage examples are only reference examples for this series. Support cannot be offered for each program. Moreover, some information of the communication between the camera and browser is not disclosed.

About the access levels

In this manual, "Live" and "Admin" are defined as the access levels. The necessity of the ID/password during CGI execution is changed from the User auth. menu of the remote camera.

When User auth. is OFF (factory settings):

Live (Video acquisition and camera control) ... Authentication not necessary

Admin (All SETUP controls) ... ID/password for Administrator authority are necessary

When User auth. is ON:

Live (Video acquisition and camera control) ... ID/password for camera control

or Administrator authority are necessary

Admin (All SETUP controls) ID/password for Administrator authority are necessary

About the priority mode

The type of CGI that can be executed and the range of parameter values differ depending on the priority mode of the remote camera.

For details, see the instruction manual.

Example) When the priority mode (/cgi-bin/set_priority_mode, /cgi-bin/get_priority_mode) is SD priority => Control cannot be performed for H.264 (1) to (4).

About the types and range of parameter values

The type of CGI that can be executed and the range of parameter values differ depending on the model. For details, see the instruction manual.

Example) Selection of 3840 x 2160

=> Enabled only in UE70 series.

2. CGI List for Video Transmission

2.1. Transmission User Management

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Transmission user	/cgi-bin/getuid	FILE	2	2 (Fixed)
management		vcodec	jpeg	jpeg: During JPEG transmission
			h264	h264: During H.264(1) transmission
			h264_2	h264_2: During H.264(2)
				transmission
			h264_3	h264_3: During H.264(3)
				transmission
			h264_4	h264_4: During H.264(4)
				transmission
		reply	browser	Command response format
			info	specification (can be omitted)
				browser: for the camera browser
				info: for the application

Usage example) Acquisition of user ID (during H264(1) transmission) http://192.168.0.10/cgi-bin/getuid?FILE=2&vcodec=h264

The response data is as shown below.

UID=< User ID >[CR][LF]

ImageFormat=< Video format >[CR][LF]

ImageCaptureMode=< Image Capture Mode >[CR][LF]

ratio=< Aspect ratio >[CR][LF]

Maxfps=< Max fps >[CR][LF]

StreamMode=< Stream mode >[CR][LF]

iBitrate=< H.264 bitrate >[CR][LF]

iResolution=< H.264 resolution >[CR][LF]

iQuality=<H.264 quality >[CR][LF]

sDelivery=< setting >[CR][LF]

iUniPort=< Unicast port number >[CR][LF]

iMultiAdd1=< 1st octet of multicast address >[CR][LF]

iMultiAdd2=< 2nd octet of multicast address >[CR][LF]

iMultiAdd3=< 3rd octet of multicast address >[CR][LF]

iMultiAdd4=< 4th octet of multicast address >[CR][LF]

iMultiAdd=< multicast address >[CR][LF]

iMultiPort=< Multicast port number >[CR][LF]

aEnable=< Audio mode>[CR][LF]

aEnc=< Audio enc >[CR][LF]

```
aBitrate=< Audio bit rate >[CR][LF]
aBitrate2=< Audio bit rate >[CR][LF]
aInterval=< Audio input interval >[CR][LF]
alnPort=< Audio unicast port number >[CR][LF]
aOutInterval=< Audio output interval >[CR][LF]
aOutPort=< Audio output port >[CR][LF]
aOutStatus=< Audio output status >[CR][LF]
aOutUID=< Audio output UID >[CR][LF]
ePort=< Event notification port number >[CR][LF]
sAlarm=< Alarm status >[CR][LF]
SDrec=< Recording status >[CR][LF]
SDrec2=< Recording status >[CR][LF]
sAUX=< Aux status >[CR][LF]
iHttpPort=< HTTP port number >[CR][LF]
iMultiAuto_h264=< Multicast auto H.264(1) >[CR][LF]
iMultiAuto_h264_2=< Multicast auto H.264(2) >[CR][LF]
iMultiAuto_h264_3=< Multicast auto H.264(3) >[CR][LF]
iMultiAuto_h264_4=< Multicast auto H.264(4) >[CR][LF]
sRtspMode_h264=< Control mode H.264(1) >[CR][LF]
sRtspMode_h264_2=< Control mode H.264(2) >[CR][LF]
sRtspMode h264 3=< Control mode H.264(3) >[CR][LF]
sRtspMode_h264_4=< Control mode H.264(4) >[CR][LF]
```

The description of the response data is as shown below.

Item	Value of response	Description
UID	Numeric value	User ID
ImageFormat	jpeg,	During JPEG transmission
	h264,	During H.264(1) transmission
	h264_X	During H.264(X) transmission
ImageCaptureMode	2m	Fixed value
ratio	16_9	Fixed value
Maxfps	30, 60	Max. frame rate
StreamMode	1	Fixed value
iBitrate	Numeric value	Bit rate setting of H.264
iResolution	320, 640, 1280, 1920,	Horizontal resolution setting of H.264
	3840 (*1)	(*1): Only for UE70 series
iQuality	fine, low	Image quality setting of H.264
sDelivery	uni,	uni: unicast (auto)
	multi,	multi: multicast
	uni_manual	uni_manual: unicast (manual)
iUniPort	1024 to 50000	Unicast port number (image)
iMultiAdd1	224 to 239	First octet of multicast address
iMultiAdd2	0 to 255	Second octet of multicast address
iMultiAdd3	0 to 255	Third octet of multicast address
iMultiAdd4	0 to 255	Fourth octet of multicast address

Item	Value of response	Description
iMultiAdd	(IP address)	H.264 multicast address
iMultiPort	Numeric value	Multicast port number
aEnable	off, in	off: Audio OFF
		in: Audio ON (reception)
aEnc	2	Fixed value (2: AAC)
aBitrate	128,96, 64	Bit rate setting of audio
aBitrate2	64	Fixed value
alnterval	20	Fixed value
alnPort	1024 to 50000	Unicast port number (audio)
aOutInterval	640	Fixed value
aOutPort	34004	Fixed value
aOutStatus	off	Fixed value
aOutUID	0	Fixed value
ePort	31004	Fixed value
sAlarm	off	Fixed value
SDrec	disable	Fixed value
SDrec2	disable	Fixed value
sAUX	disable	Fixed value
iHttpPort	Numeric value	HTTP port number
iMultiAuto_h264	0	Fixed value
iMultiAuto_h264_2	0	Fixed value
iMultiAuto_h264_3	0	Fixed value
iMultiAuto_h264_4	0	Fixed value
sRtspMode_h264	0	Fixed value
sRtspMode_h264_2	0	Fixed value
sRtspMode_h264_3	0	Fixed value
sRtspMode_h264_4	0	Fixed value

2.2. Device Information Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Device information acquisition	/cgi-bin/getinfo	FILE	1	1 (Fixed)

Usage example) Acquisition of user ID (during H264(1) transmission) http://192.168.0.10/cgi-bin/getinfo?FILE=1

The response data is as shown below.

MAC=< Mac address >[CR][LF]

SERIAL=< Serial number >[CR][LF]

VERSION=< Firmware version >[CR][LF]

NAME=< Model name >[CR][LF]

SDrec=< Recording status >[CR][LF]

SDrec2=< Recording status >[CR][LF]

sAlarm=< Alarm status >[CR][LF]

sAUX=< Aux status >[CR][LF]

ePort=< Event notification port number >[CR][LF]

aEnable=< Audio mode>[CR][LF]

aEnc=< Audio enc >[CR][LF]

aBitrate=< Audio bit rate >[CR][LF]

aBitrate2=< Audio bit rate >[CR][LF]

aInterval=< Audio input interval >[CR][LF]

aOutInterval=< Audio output interval >[CR][LF]

aOutPort=< Audio output port >[CR][LF]

aOutStatus=< Audio output status >[CR][LF]

aOutUID=< Audio output UID >[CR][LF]

alnPort_h264=< Audio with H.264 1st stream unicast port number >[CR][LF]

alnPort h264 2=< Audio with H.264 2nd stream unicast port number >[CR][LF]

alnPort_h264_3=< Audio with H.264 3rd stream unicast port number >[CR][LF]

alnPort_h264_4=< Audio with H.264 4th stream unicast port number >[CR][LF]

sRtspMode_h264=< Control mode H.264(1) >[CR][LF]

sRtspMode_h264_2=< Control mode H.264(2) >[CR][LF]

sRtspMode_h264_3=< Control mode H.264(3) >[CR][LF]

sRtspMode_h264_4=< Control mode H.264(4) >[CR][LF]

ImageCaptureMode=< limage Capture Mode >[CR][LF]

ratio=< Aspect ratio >[CR][LF]

Maxfps=< Max fps >[CR][LF]

StreamMode=< Stream mode >[CR][LF]

iTransmit_h264=< H.264 1st stream ON/OFF setting >

sDelivery h264=< H.264 1st stream setting >[CR][LF]

iBitrate_h264=< H.264 1st stream bit rate >[CR][LF]

iResolution_h264=< H.264 1st stream resolution >[CR][LF]

iQuality_h264=< H.264 1st stream quality >[CR][LF] iMultiAuto_h264=< Multicast auto H.264(1) >[CR][LF] iTransmit_h264_2=< H.264 2nd stream ON/OFF setting > sDelivery_h264_2=< H.264 2nd stream setting >[CR][LF] iBitrate h264 2=< H.264 2nd stream bit rate >[CR][LF] iResolution_h264_2=< H.264 2nd stream resolution >[CR][LF] iQuality h264 2=< H.264 2nd stream quality >[CR][LF] iMultiAuto h264 2=< Multicast auto H.264(2) >[CR][LF] iTransmit_h264_3=< H.264 3rd stream ON/OFF setting > sDelivery_h264_3=< H.264 3rd stream setting >[CR][LF] iBitrate_h264_3=< H.264 3rd stream bit rate >[CR][LF] iResolution_h264_3=< H.264 3rd stream resolution >[CR][LF] iQuality_h264_3=< H.264 3rd stream quality >[CR][LF] iMultiAuto_h264_3=< Multicast auto H.264(3) >[CR][LF] iTransmit_h264_4=< H.264 4th stream ON/OFF setting > sDelivery_h264_4=< H.264 4th stream setting >[CR][LF] iBitrate_h264_4=< H.264 4th stream bit rate >[CR][LF] iResolution_h264_4=< H.264 4th stream resolution >[CR][LF] iQuality_h264_4=< H.264 4th stream quality >[CR][LF] iMultiAuto_h264_4=< Multicast auto H.264(4) >[CR][LF]

The description of the response data is as shown below.

Item	Value of response	Description	
MAC	XX-XX-XX-XX-XX	MAC address	
SERIAL	XXXXXXXX	Product serial number	
VERSION		Software version	
NAME	AW-XXXX	Product number	
SDrec	disable	Fixed value	
SDrec2	disable	Fixed value	
sAlarm	off	Fixed value	
sAUX	off	Fixed value	
ePort	31004	Fixed value	
aEnable	off, in	off: Audio OFF	
		in: Audio ON (reception)	
aEnc	2	Fixed value (2: AAC)	
aBitrate	128,96,64	Bit rate setting of audio	
aBitrate2	64	Fixed value	
alnterval	20	Fixed value	
aOutInterval	640	Fixed value	
aOutPort	34004	Fixed value	
aOutStatus	off	Fixed value	
aOutUID	0	Fixed value	
alnPort_h264	1024 to 50000	H.264(1) Audio reception port number	
alnPort_h264_2	1024 to 50000	H.264(2) Audio reception port number	
alnPort_h264_3	1024 to 50000	H.264(3) Audio reception port number	

alnPort h264 4	1024 to 50000	H.264(4) Audio reception port number
sRtspMode h264	0	Fixed value
sRtspMode_h264_2	0	Fixed value
sRtspMode_h264_3	0	Fixed value
sRtspMode_h264_4	0	Fixed value
ImageCaptureMode	2m	Fixed value
ratio	16_9	Fixed value
Maxfps	30, 60	Max. frame rate
StreamMode	1	Fixed value
iTransmit_h264	1	Fixed value
sDelivery_h264	uni,	uni: Unicast (auto)
	multi,	multi: Multicast
	uni_manual	uni_manual Unicast (manual)
iBitrate_h264	Numeric value	Bit rate setting of H.264(1)
iResolution_h264	320, 640, 1280, 1920,	Horizontal resolution setting of H.264(1)
	3840 (*1)	(*1): Only for UE70 series
iQuality_h264	fine, low	Image quality setting of H.264(1)
iMultiAuto_h264	0	Fixed value
iTransmit_h264_2	see.H.264(1)	see.H.264(1)
sDelivery_h264_2		
iBitrate_h264_2		
iResolution_h264_2		
iQuality_h264_2		
iMultiAuto_h264_2		
iTransmit_h264_3	see.H.264(1)	see.H.264(1)
sDelivery_h264_3		
iBitrate_h264_3		
iResolution_h264_3		
iQuality_h264_3		
iMultiAuto_h264_3		
iTransmit_h264_4	see.H.264(1)	see.H.264(1)
sDelivery_h264_4		
iBitrate_h264_4		
iResolution_h264_4		
iQuality_h264_4		
iMultiAuto_h264_4		

2.3. Camera-specific Information (Capability) Acquisition

Method : POST/ GET

Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Camera-specific information	/cgi-bin/get_capability	-	-	Explained under the
(Capability) acquisition				next item

Usage example) Camera-specific information (Capability) acquisition http://192.168.0.10/cgi-bin/get_capability

The description of the response data is as shown below.

Group name	Parameter name	Parameter value	Description
common	capability_version	1.00	Version of the capability format
	category	camera	Category
video_server.basic	type	dome	Product shape
	fisheye	no	Fisheye camera
video_server.basic.analogue	supported	ntsc,pal	Supported video signals of the analog
_input			camera (encoder)
video_server.cam_ctrl.ptz	supported	yes	Availability of PTZ function
	zoom	30	Zoom magnification
	el_zoom	40	Electronic zoom magnification
	command	camctrl	Supported PTZ commands
		direct_16	
		direct_256d	
		direct_256r	
video_server.cam_ctrl.ptz.pa	type	limited	Pan operation
n_range			limited: Endless operation not possible
	abs_value	-	Not supported
video_server.cam_ctrl.ptz.tilt	value	-	Not supported
_range			
video_server.cam_ctrl.brightn	supported	yes	Support for brightness control command
ess	command	camctrl_bright	Types of supported commands
		camctrl_IRIS	
video_server.cam_ctrl.abf	supported	no	Support for ABF command
video_server.cam_ctrl.focus	supported	yes	Support for focus command
video_server.cam_ctrl.auto_f	supported	yes	Support for auto-focus command
ocus			
video_server.cam_ctrl.bw	supported	no	Support for black and white selection
			command
video_server.cam_ctrl.auto_	supported	no	Support for auto mode
mode			
video_server.cam_ctrl.preset	supported	yes	Support for preset movement command
	number	100	Number of preset positions

video_server.image sensor number - Not supported video_server.image sensor aspect_ratio 16_9 Aspect ratio of sensor fog - Not supported video_server.image format peg, mjpeg, h264 Supported imaging mode video_server.image.jpeg resolution 1920x1080, 200x180 Resolution parameters supported in the JPEG1 shot video_server.image.jpeg.resolution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.resolution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max _size 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,2 Max. data size of one JPEG image per resolution video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,2 Max. data size of one JPEG image per resolution video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,2 Max. data size of one JPEG image quality setting is resolution video_server.image.jpeg.max _size <td< th=""><th>Group name</th><th>Parameter name</th><th>Parameter value</th><th>Description</th></td<>	Group name	Parameter name	Parameter value	Description
sd - Not supported fog - Not supported video_server.image format jpeg, mjpeg, h264 Supported image transmission format video_server.image.jpeg resolution 1920x1080, 1280x720, 640x360, 320x180 Resolution parameters supported in the JPEG1 shot video_server.image.jpeg.resol lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Image quality parameters supported in the JPEG1 shot video_server.image.jpeg.resol lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.resol lution_each_mode_all 1920 x 1080 240,240,240,240.2 Max. data size of one JPEG image per resolution video_server.image.jpeg.max_size 1920 x 1080 240,240,240,240.2 Max. data size of one JPEG image per resolution video_server.image.jpeg.max_size 1280 x 720 180,180,180,180,180,180,180,180,180,180,	video_server.peripheral.io	number	-	Not supported
video_server.image fog hic - Not supported video_server.image format jpeg, mipeg, h264 Supported image transmission format video_server.image.jpeg resolution 1920x1080, 280x720, 640x360, 320x180 Resolution parameters supported in the JPEG1 shot video_server.image.jpeg.resolution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Image quality parameters supported in the JPEG1 shot video_server.image.jpeg.resolution_each_mode_all 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max_size 1920 x 1080 240,240,240,240,240, 240, 240, 240, 240,	video_server.image.sensor	aspect_ratio	16_9	Aspect ratio of sensor
video_server.image format jpeg, mjpeg, h264 Supported image transmission format video_server.image.jpeg resolution 1920x1080, 1280x720, 640x360, 320x180 Resolution parameters supported in the JPEG1 shot video_server.image.jpeg.resol lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.resol lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.resol lution_each_mode_all 1920 x 1080 240,240,240,240,2 Max. data size of one JPEG image per resolution video_server.image.jpeg.max_size 1920 x 1080 240,240,240,240,2 Max. data size of one JPEG image per resolution video_server.image.jpeg.max_size 180,180,180,180,180,180,180,180,180,180,		sd	-	Not supported
video_server image format mode jpeg, mjpeg, h264 Supported image transmission format mode video_server image.jpeg resolution 1920x1080, 1280x720, 640x360, 320x180 Resolution parameters supported in the JPEG1 shot video_server.image.jpeg.reso lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.reso lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max _ size 1920 x 1080 240,240,240,240,240,240,240,240,240,240,		fog	-	Not supported
wideo_server.image.jpeg resolution 1920x1080, 1280x720, 640x360, 320x180 Resolution parameters supported in the JPEG1 shot video_server.image.jpeg.reso lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Image quality parameters supported in the JPEG1 shot video_server.image.jpeg.reso lution_each_mode_all 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max_size 1920 x 1080 240,240,240,240,240, 240, 240, 240, 240,		hlc	-	Not supported
video_server.image.jpeg resolution 1920x1080, 1280x720, 640x360, 320x180 Resolution parameters supported in the JPEG1 shot video_server.image.jpeg.reso lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.reso lution_each_mode_all 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,2 40,22 40,120,120,120,120,120,120,120,120,120,12	video_server.image	format	jpeg, mjpeg, h264	Supported image transmission format
1280x720, 640x360, 320x180 PEG1 shot		mode	2m_r16_9	Supported imaging mode
Video_server.image.jpeg.reso Ution_each_mode	video_server.image.jpeg	resolution	1920x1080,	Resolution parameters supported in the
Video_server.image.jpeg.reso Ution_each_mode			1280x720,	JPEG1 shot
video_server.image.jpeg.reso lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.reso lution_each_mode_all 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,2 40,120,120,120,120,12 0,120 Max. data size of one JPEG image per resolution unit [Kbyte] 1280 x 720 180,180,180,180,180,180,180,180,180,180,			640x360, 320x180	
video_server.image.jpeg.reso lution_each_mode 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.reso lution_each_mode_all 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,2 40,120,120,120,120,120,120,120,120,120,12		quality	0 to 9	Image quality parameters supported in the
lution_each_mode 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.resolution_each_mode_all 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max_size 1920 x 1080 240,240,240,2240,2 40,2240,2 40,220,120,120,120,120,120,120,120,120 Max. data size of one JPEG image per resolution Unit [Kbyte] 1280 x 720 180,180,180,180,1 80,1 80,90,90,90,90,90,90,90,90,90,90,90,90,90				JPEG1 shot
Video_server.image.jpeg.reso Lution_each_mode_all	video_server.image.jpeg.reso	2m_r16_9	1920x1080,	Transmission-enabled JPEG resolution
video_server.image.jpeg.reso lution_each_mode_all 2m_r16_9 1920x1080, 1280x720, 640x360, 320x180 Transmission-enabled JPEG resolution video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,240,240,240,240,240,240,	lution_each_mode		1280x720,	
			640x360, 320x180	
video_server.image.jpeg.max _size 1920 x 1080 240,240,240,240,240,2 do,120,120,120 resolution Unit [Kbyte] Max. data size of one JPEG image per resolution Unit [Kbyte] 1280 x 720 180,180,180,180,180,1 80,90,90,90,90,90 Values are separated by a comma and enumerated Configuration: <value 1="">,<value 2="">,<value 3="">,<value 4="">,<value 5="">,<value 6="">, ,,, ,<value (n)="">, ,, 640 x 360 60,60,60,60,60,60,30, 30,30,30,30,30,30,30,30,30,30,30,30,30,3</value></value></value></value></value></value></value>		2m_r16_9	1920x1080,	Transmission-enabled JPEG resolution
video_server.image.jpeg.max _ size 1920 x 1080 240,240,240,240,2 40,2 40,2 40,2 40,2 40	lution_each_mode_all		·	
1280 x 720				
1280 x 720	video_server.image.jpeg.max	1920 x 1080		
1280 x 720	_size			
1280 x 720			0,120	Unit [Kbyte]
1280 x 720				
80,90,90,90,90,90 Configuration: <value 1="">,<value 2="">,<value 3="">,<value 4="">,<value 5="">,<value 6="">, ,,, <value (n)="">, ,, 640 x 360</value></value></value></value></value></value></value>		1280 x 720	180,180,180,180,1	
2>, <value 3="">,<value 4="">,<value 5="">,<value 6="">, ,,, ,<value (n)="">, ,, When video_server.image.jpeg.quality (JPEG image quality setting parameter) is 0,1,2,3,4,5,6,7,8,9, it indicates the below-mentioned meaning.</value></value></value></value></value>			80,90,90,90,90,90	
Solution				1
640 x 360 60,60,60,60,60,30, 30,30,30,30, When video_server.image.jpeg.quality (JPEG image quality setting parameter) is 0,1,2,3,4,5,6,7,8,9, it indicates the below-mentioned meaning. <value 1="">: Max. data size when the JPEG image quality setting is "0" <value 2="">: Max. data size when the JPEG image quality setting is "1" <value 10="">: Max. data size when the JPEG image quality setting is "9" video_server.image.mjpeg resolution 1920x1080, 1280x720, 640x360, 320x180 quality Image quality parameters supported in the JPEG stream</value></value></value>				
30,30,30,30, 30,30,30,30, (JPEG image quality setting parameter) is 0,1,2,3,4,5,6,7,8,9, it indicates the below-mentioned meaning. Value 1>: Max. data size when the JPEG image quality setting is "0" Value 2>: Max. data size when the JPEG image quality setting is "1" Value 10>: Max. data size when the JPEG image quality setting is "9" video_server.image.mjpeg resolution 1920x1080, 1280x720, 640x360, 320x180 quality 0 to 9 Image quality parameters supported in the		640 × 360	60 60 60 60 60 30	1
video_server.image.mjpeg Video_server.image.mjpeg Quality Q		040 X 300		
below-mentioned meaning. Value 1>: Max. data size when the JPEG image quality setting is "0" Value 2>: Max. data size when the JPEG image quality setting is "1" Video_server.image.mjpeg Value 1>: Max. data size when the JPEG image quality setting is "0" Value 1>: Max. data size when the JPEG image quality setting is "1" Note of the server.image and			30,30,30,30,	
320 x 180 320 x 180 30,30,30,30,30,15, 15,15,15 320 x 180 30,30,30,30,30,30,15, 15,15,15 4 Value 1>: Max. data size when the JPEG image quality setting is "0" 4 Value 2>: Max. data size when the JPEG image quality setting is "1" 4 Value 1>: Max. data size when the JPEG image quality setting is "1" 5 Value 1>: Max. data size when the JPEG image quality setting is "1" 7 Value 1>: Max. data size when the JPEG image quality setting is "1" 8 Value 1>: Max. data size when the JPEG image quality setting is "1" 8 Value 1>: Max. data size when the JPEG image quality setting is "1" 8 Value 1>: Max. data size when the JPEG image quality setting is "1" 8 Value 1>: Max. data size when the JPEG image quality setting is "1" 8 Value 1>: Max. data size when the JPEG image quality setting is "1" 8 Value 1>: Max. data size when the JPEG image quality setting is "1" 8 Value 1>: Max. data size when the JPEG image quality setting is "0" 8 Value 1>: Max. data size when the JPEG image quality setting is "0" 8 Value 1>: Max. data size when the JPEG image quality setting is "0" 8 Value 2>: Max. data size when the JPEG image quality setting is "0" 8 Value 2>: Max. data size when the JPEG image quality setting is "0" 8 Value 1>: Max. data size when the JPEG image quality setting is "0" 8 Value 1>: Max. data size when the JPEG image quality setting is "0" 8 Value 1>: Max. data size when the JPEG image quality setting is "0" 9 Value 2>: Max. data size when the JPEG image quality setting is "0" 9 Value 2>: Max. data size when the JPEG image quality setting is "0" 9 Value 1>: Max. data size when the JPEG image quality setting is "0" 19 Value 1>: Max. data size when the JPEG image quality setting is "0" 19 Value 1>: Max. data size when the JPEG image quality setting is "0" 19 Value 1>: Max. data size when the JPEG image quality setting is "0" 19 Value 1>: Max. data size when the JPEG image quality setting is "0" 19 Value 1>: Max. data size when the JPEG image quality setting is "0" 19 Value 1>: Max. data size wh				
video_server.image.mjpeg resolution quality 130,30,30,30,30,30,15, 15,15,15 16 17 18 18 19 19 19 19 19 19 19 19				
video_server.image.mjpeg resolution resolution quality 15,15,15,15 <value 2="">: Max. data size when the JPEG image quality setting is "1" <value 10="">: Max. data size when the JPEG image quality setting is "9" resolution parameters supported in the JPEG image quality setting is "9" 1280x720,</value></value>		320 x 180	30,30,30,30,30,15,	
image quality setting is "1" Value 10>: Max. data size when the JPEG image quality setting is "9" video_server.image.mjpeg resolution 1920x1080, 1280x720, 640x360, 320x180 quality 0 to 9 Image quality setting is "1" Value 10>: Max. data size when the JPEG image quality setting is "9" Resolution parameters supported in the JPEG stream 10 to 9 Image quality parameters supported in the			15,15,15,15	
video_server.image.mjpeg video_server.image.mjpeg resolution 1920x1080, 1280x720, 640x360, 320x180 quality 10 to 9				
video_server.image.mjpeg video_server.image.mjpeg resolution 1920x1080, 1280x720, 640x360, 320x180 quality 10>: Max. data size when the JPEG image quality setting is "9" Resolution parameters supported in the JPEG stream fundamental supported in the Image quality parameters supported in the				
video_server.image.mjpegresolution1920x1080, 1280x720, 640x360, 320x180Resolution parameters supported in the JPEG streamquality0 to 9Image quality parameters supported in the				
video_server.image.mjpeg resolution 1920x1080, 1280x720, 640x360, 320x180 Resolution parameters supported in the JPEG stream quality 0 to 9 Image quality parameters supported in the				
1280x720, JPEG stream 640x360, 320x180 quality 0 to 9 Image quality parameters supported in the	video_server.image.mipeg	resolution	1920x1080,	
640x360, 320x180 quality 0 to 9 Image quality parameters supported in the				1
quality 0 to 9 Image quality parameters supported in the			·	
		quality		Image quality parameters supported in the
0.200.00				JPEG stream

Group name	Parameter name	Parameter value	Description
	framerate	1 to 30	Frame rates supported in the JPEG
			stream
			Rounded down to the nearest whole
			number
			NTSC: 1 to 30
			PAL: 1 to 25
video_server.image.mjpeg.m	2m_r16_9	30	Max. frame rate of JPEG stream
ax_framerate			
video_server.image.mjpeg.re	2m_r16_9	1920x1080,	Setting-enabled JPEG resolution
solution_each_mode		1280x720,	
		640x360, 320x180	
video_server.image.mjpeg.re	2m_r16_9	1920x1080,	Setting-enabled JPEG resolution
solution_each_mode_all		1280x720,	
		640x360, 320x180	
video_server.image.h264	resolution	3840x2160(*1),	Resolution parameters supported in
		1920x1080,	H.264(1)
		1280x720,	(*1): Only for UE70 series
		640x360, 320x180	
	stream_mode	bitrate, framerate,	Transmission modes supported in
		best_effort	H.264(1)
	quality	fine, normal	Image quality parameters supported in
			H.264(1)
	bandwidth	512,768,1024,153	Bit rate parameters supported in H.264(1)
		6,2048,3072,4096,	(*1): Only for UE70 series
		6144,8192,10240,	
		12288,14336,	
		16384,20480,	
		24576,	
		32768(*1),	
		40960(*1),	
		51200(*1)	
	framerate	5,15(12.5),30(25),	Frame rate parameters supported in
		60(50)	H.264(1)
			* The values within () are for the case
			when the system frequency is 50 Hz
video_server.image.h264.res	2m_r16_9	3840x2160(*1),	Supported H.264(1) resolutions
olution_each_mode		1920x1080,	(*1): Only for UE70 series
		1280x720,	
		640x360, 320x180	
video_server.image.h264.ma	2m_r16_9	60	Supported max. H.264(1) frame rate
x_framerate			
video_server.image.h264-2	Same as H264-1		
video_server.image.h264-2.r			
esolution_each_mode			
video_server.image.h264-2.			
max_framerate			

Group name	Parameter name	Parameter value	Description
video_server.image.h264-3			
video_server.image.h264-3.r			
esolution_each_mode			
video_server.image.h264-3.			
max_framerate			
video_server.image.h264-4			
video_server.image.h264-4.r			
esolution_each_mode			
video_server.image.h264-4.			
max_framerate			
video_server.audio	transmission	input	Audio transmission setting mode
video_server.audio.audio_inp	number	1	Audio microphone input number
ut	encode_type	aac-1c_64K	Supported audio input encoding type
		aac-1c_96K	
		aac-1c_128K	
video_server.sdcard	supported	yes	Support for SD memory card function
	media_type	sd, sdhc, sdxc	Supported SD memory card type
video_server.sdcard.replay_	supported	no	Support for the function for playing back
mp4			MP4 files saved in the SD memory card
			inside the camera
video_server.network	nw_bandwidth	1024,2048,4096,8	Parameters supported in the overall
		192,16384,32768	transmission volume setting
video_server.network.ipv6	supported	yes	IPv6 support status
video_server.network.https	supported	yes	HTTPS (SSL) support status
video_server.vmd	supported	no	VMD support status

2.4. JPEG-based Image Transmission

Method : GET Access level : Live

Access level :	Live			
CGI item name	URL	Parameter	Parameter value	Description
IDEO image	/a ai laire/ire a ar	name	Otant	starti Otarta IDEO imaga transpariacian
JPEG image	/cgi-bin/jpeg	connect	Start	start: Starts JPEG image transmission
transmission			stop	stop: Stops JPEG image transmission
(MJPEG)		framerate	1	1 fps
			5	5 fps
			15(12.5)	15 (12.5) fps
			30(25)	30 (25) fps
				The values within () are for the case
				when the system frequency is 50 Hz
		resolution	320	320: 320 x 180
			640	640: 640 x 360
			1280	1280: 1280 x 720
			1920	1920: 1920 x 1080
		UID	Numeric value	User ID
				* UID acquired by /cgi-bin/getuid
JPEG image	/cgi-bin/mjpeg	resolution	320	320: 320 x 180
transmission			640	640: 640 x 360
(MJPEG)			1280	1280: 1280 x 720
			1920	1920: 1920 x 1080
		framerate	1	1 fps
			5	5 fps
			15(12.5)	15 (12.5) fps
			30(25)	30 (25) fps
				The values within () are for the case
				when the system frequency is 50 Hz
JPEG image 1	/cgi-bin/view.c	action	Snapshot	snapshot: Acquires one JPEG image
shot request	gi		start	start: Starts JPEG transmission
	9.		stop	stop: Stops JPEG transmission
		n	Numeric value	Dummy for disabling cache
Resolution setting	/cgi-bin/aw ptz	cmd	%23RZL1&res=1	%23RZL1&res = 1: 320 x 180 setting
for view.cgi	/cgi-bii/aw_ptz	Citia	/0251\ZLT&IE3=1	70251(2E10(163 = 1. 520 x 100 3etting
ioi view.cgi			%23RZL0&res=1	%23RZL0&res = 1: 640 x 360 setting
JPEG image 1	/cgi-bin/camer	resolution	320	320: 320 x 180
shot request	а		640	640: 640 x 360
			1280	1280: 1280 x 720
			1920	1920: 1920 x 1080
		page	Numeric value	Dummy for disabling cache
Playback data	/cgi-bin/view_p	-	-	Acquires one playback image
transmission	b.cgi			(H.264/JPEG converted)

[Notes]

In a remote camera, various techniques are provided for acquisition of a JPEG video. Use the technique suitable to your purpose.

MJPEG

By continuously displaying the videos that arrive, a movie display can be realized.

The frame rate is decided based on the arguments.

Depending on the software and hardware at the receiving side, some frame rates may not be supported.

JPEG image 1 shot

By repeating the processes of acquisition, display, and standby for a single JPEG image, a movie display can be realized.

The frame rate is decided according to the standby time in the software and hardware at the receiving side.

The characteristics of each CGI of MJPEG are as described below.

/cgi-bin/jpeg

When CGI is called once, the MJPEG stream is transmitted continuously. Before calling, the acquisition of UID with /cgi-bin/getuid is necessary.

In Internet Explorer, the plug-in software is used when calling JPEG(1) to (3). Specific usage examples and sequences are described in the next chapter.

/cgi-bin/mjpeg

When CGI is called once, the MJPEG stream is transmitted continuously. Before calling, the acquisition of UID with /cgi-bin/getuid is not necessary.

It is used when calling JPEG from some mobile terminals.

In Safari, movie display is possible by entering only this CGI in the URL field of the browser. Not supported by Internet Explorer.

Usage example) When acquiring a 320 x 180 video in 30 fps in the MJPEG format: http://192.168.0.10/cgi-bin/mjpeg?resolution=320&framerate=30

Usage example) When acquiring a 640 x 360 video in 15 fps in the MJPEG format: http://192.168.0.10/cgi-bin/mjpeg?resolution=640&framerate=15

Usage example) When acquiring a video of approx. 5 fps in the MJPEG format (parameter omitted): http://192.168.0.10/cgi-bin/mjpeg

The characteristics of each CGI of JPEG image 1 shot are as described below.

/cgi-bin/view.cgi

When CGI is called once, only one JPEG image is transmitted.

Before calling, the acquisition of UID with /cgi-bin/getuid is not necessary.

The resolution can be set with the /cgi-bin/aw_ptz?cmd=%23RZLx&res=1 command.

Not supported by other than $640 \times 360 / 320 \times 180$.

Used when calling a JPEG image without the use of plug-in software in Internet Explorer.

Usage example) When acquiring a 320 x 180 video through a JPEG image 1 shot request:

http://192.168.0.10/cgi-bin/aw_ptz?cmd=%23RZL1&res=1

http://192.168.0.10/cgi-bin/view.cgi?action=start

http://192.168.0.10/cgi-bin/view.cgi?action=snapshot&n=3333

<Appropriate standby time>

http://192.168.0.10/cgi-bin/view.cgi?action=snapshot&n=3334

<Appropriate standby time>

http://192.168.0.10/cgi-bin/view.cgi?action=snapshot&n=3335

While the "start" command is mandatory after turning the power supply ON, the "stop" command is not mandatory. The "start" command may be issued any number of times without any problem.

/cgi-bin/camera

When CGI is called once, only one JPEG image is transmitted.

Before calling, the acquisition of UID with /cgi-bin/getuid is not necessary.

In Internet Explorer, the plug-in software is used when acquiring a screen shot.

The notes common for each CGI are as described below.

When a video is acquired simultaneously by several PCs and receivers, the best effort judgment is performed at the camera side. Therefore, the expected frame rate display may not be achieved.

When the WEB menu/Video over IP/JPEG/JPEG transmission are OFF, the response may be in the form of a pitch black JPEG image.

As for the resolution and frame rate, the content registered in the WEB menu/Video over IP/JPEG is given priority.

Therefore, even if the resolution is specified in the arguments, the response may be issued with an unexpected resolution and frame rate.

Example) If JPEG(1) = $640 \times 360/30$ fps, JPEG(2) = $1280 \times 720/5$ fps, JPEG(3) = $320 \times 180/15$ fps, /cgi-bin/mjpeg?resolution=320&framerate=15

=> As instructed, the response is in the form of content of the 320 x 180 JPEG(3).

/cgi-bin/mjpeg?resolution=640&framerate=15

=> As instructed, the response is issued by subtracting the frame rate from the content of the 640 x 360 JPEG(1)

/cgi-bin/mjpeg?resolution=1280&framerate=15

=> The response is issued with a resolution of 1280 x 720, but the frame rate is 5 fps, which is the upper limit of JPEG(2).

/cgi-bin/mjpeg?resolution=320&framerate=1920


=> Because no content is registered in JPEG(1) to (3), the response is issued with the resolution of JPEG(1) and a frame rate of 5 fps.

/cgi-bin/mjpeg

=> Because there are no parameters, the response is issued with the resolution of JPEG(1) and a frame rate of 5 fps.


Note that if you use /cgi-bin/aw_ptz?cmd=%23RZLx&res=1, the resolution of JPEG(1) changes.

2.5. Image Transmission Sequence based on MJPEG



MJPEG Sequence

2.6. Image Transmission Sequence based on JPEG Image 1 shot



20

2.7. H264/AUDIO-based Image Transmission

Method : GET Access level : Live

Access level : Live				
CGI item name	URL	Parameter name	Parameter value	Description
H.264 image	/cgi-bin/h264	my_port	Numeric value	Reception port number of H.264
transmission				* This parameter cannot be omitted if
				unicast is set.
		connect	start	start: Starts H.264 transmission
			stop	stop: Stops H.264 transmission
		protocol	rtp	rtp: RTP format (can be omitted)
		UID	Numeric value	User ID
				* UID acquired by /cgi-bin/getuid
		stream	1	1: Stream 1
			2	2: Stream 2
			3	3: Stream 3
			4	4: Stream 4
Audio transmission	/cgi-bin/audio	connect	start	start: Starts audio transmission
			stop	stop: Stops audio transmission
		protocol	rtp	rtp: RTP transmission
			http	http: HTTP transmission
		my_port	Numeric value	Reception port number of audio data
				*Only when protocol = rtp
				Can be omitted during HTTP
				transmission
		UID	Numeric value	User ID
				* UID acquired by /cgi-bin/getuid
		mode	in	in: Fixed
Volume control	/cgi-bin/audio	in_vol	low	low: Low
	_vol		mid	mid: Middle
			high	high: High
			line_low	line_low: Line Low
			line_mid	line_mid: Line Middle
			line_high	line_high: Line High
Keep alive	/cgi-bin/keep_	mode	h.264	h.264: H.264 keep alive
	alive		h.264_2	h.264_2: H.264(2) keep alive
			h.264_3	h.264_3: H.264(3) keep alive
			h.264_4	h.264_4: H.264(4) keep alive
			jpeg	jpeg: JPEG keep alive
			audio	audio: Audio keep alive
		protocol	rtp	rtp: RTP transmission
			http	http: HTTP transmission
		UID	Numeric value	User ID
				* UID acquired by /cgi-bin/getuid

CGI item name	URL	Parameter name	Parameter value	Description
		stream	1	1: Stream 1
			2	2: Stream 2
			3	3: Stream 3
			4	4: Stream 4
				* Can be omitted


Usage example) H264(1) image transmission start (when the port number is "40000" and User ID is "263") http://192.168.0.10/cgi-bin/h264?my_port=40000&connect=start&protocol=rtp&UID=263&stream=1

Usage example) Audio transmission start http://192.168.0.10/cgi-bin/audio?my_port=38004&connect=start&protocol=rtp&UID=263&mode=in

Usage example) Audio volume setting http://192.168.0.10/cgi-bin/audio_vol?in_vol=low

Usage example) Keep alive (JPEG) http://192.168.0.10/cgi-bin/keep_alive?mode=jpeg&protocol=http&UID=263

2.8. Unicast Image Transmission Sequence based on H264



H264 Sequence

3. CGI List for Camera Control

3.1. Pan/Tilt/Zoom

Method : GET Access level : Live

Access level	. LIVE		_	
CGI item name	URL	Parameter name	Parameter value	Description
Camera control	/cgi-bin/camctr	times	1	1: Return to default setting
	1		up	up: ZOOM UP one level
			down	down: ZOOM DOWN one level
			0	0: Return to default setting
		zoom	1	1: Return to default setting
			up	up: ZOOM UP one leve
			down	down: ZOOM DOWN one level
			0	0: Return to default setting
		bright	1	1: Return to default setting
			up	up: Turn brightness one level UP
			down	down: Turn brightness one level DOWN
			-2	-2: Turn brightness two levels DOWN
			0	0: Return brightness to standard value (reset)
			2	2: Turn brightness two levels UP
		iris	1	1: Return to default setting
			up	up: Turn brightness one level UP
			down	down: Turn brightness one level DOWN
			-2	-2: Turn brightness two levels DOWN
			0	0: Return brightness to standard value (reset)
			2	2: Turn brightness two levels UP
		preset	0 to 100	1 to 100: Preset position number
				0: Home position
		focus	-3, 3, on	-3: Near, 3: Far, on: Auto
		af	-3, 3, on	-3: Near, 3: Far, on: Auto
		pan	-5 to 5	A negative value indicates movement to the
				left, and a positive value indicates movement
				to the right
				* Used together with the tilt parameter
		tilt	-4 to 4	A positive value indicates downward
				movement and a negative value indicates
				upward movement
				* Used together with the pan parameter

CGI item name	URL	Parameter name	Parameter value	Description
Camera control	/cgi-bin/directc	pan	-16 to 16	A negative value indicates movement to the
direct	trl			left, and a positive value indicates movement
				to the right
				* Used together with the tilt parameter
		tilt	-16 to 16	A negative value indicates downward
				movement and a positive value indicates
				upward movement
				* Used together with the pan parameter
		zoom	-4 to 4	A negative value indicates ZOOM DOWN
				and a positive value indicates ZOOM UP
		focus	-4 to 4	A negative value indicates near and a
				positive value indicates far

^{*} This CGI is for backward compatibility. In a remote camera, the use of cgi-bin/aw_ptz enables high-functionality control. For details, see "HD Integrated Camera Interface Specifications".

4. CGI List for Various Settings

4.1. Basic Settings

Method : POST/GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Priority mode setting	/cgi-bin/set_priori	mode	ip	ip: IP priority mode
	ty_mode		sdcard	sdcard: SD card priority mode
			usb	usb: USB priority mode
			ip_4k	ip_4k: IP (4K) priority mode
			sdcard_4k	sdcard_4k: SD card (4K) priority mode
			usb_4k	usb_4k: USB (4K) priority mode
			hdmi_4k	hdmi_4k: HDMI (4K) priority mode (*1)
			ndi_hx	ndi_hx:NDI HX priority mode (*2)
Basic settings	/cgi-bin/set_basic	cam_title	String	Camera title (within 20 double-byte characters)
		plugin_	enable	Auto installation of plug-in software
		download	disable	enable: Allowed
				disable: Not allowed
		plugin_disp	0	0: Real time consideration (Off)
			1	1: Smooth display (On)

Usage example) Set the priority mode to IP http://192.168.0.10/cgi-bin/set_priority_mode?mode=ip

Usage example) Set the camera title http://192.168.0.10/cgi-bin/set_basic?cam_title=he40

(*1): Only for UE70 series

(*2): HE40 series requires Ver1.6 or later and UE70 series requires Ver1.3 or later.

4.2 Clock Settings

Method : POST/GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
NTP settings	/cgi-bin/time	time_adjust	0	0: Manual
			1	1: Synchronized with the NTP server
		ntp_addr_dhc	0	0: OFF (manual input)
		р	1	1: ON (acquired from DHCP)
		ntp_addr	String	IP address
		ntp_port	Numeric value	1 to 65535
		ntp_interval	Numeric value	1 to 24 (hours)
Clock settings	/cgi-bin/date_tim	display	0	0: off
	е		1	1: on
		date_year	2013 to 2035	Year
		date_month	1 to 12	Month
		date_day	1 to 31	Day
		date_hour	0 to 23	Hour
		date_min	0 to 59	Minutes
		date_sec	0 to 59	Seconds
		timezone	1 to 75	1 to 75
		summer_time	0	0: Summer time is not set (Out)
			1	1: Summer time is set (In)
			2	2: Summer time is auto-adjusted
				according to (Start/End) (Auto)
		start_month	1 to 12	1: January to 12: December
		start_week	1 to 5	1: First week, 2: Second week, 3:
				Third week
				4: Fourth week, 5: Last week
		start_dotw	0 to 6	0: Sunday to 6: Saturday
		start_hour	0 to 23	0 to 23
		end_month	1 to 12	1: January to 12: December
		end_week	1 to 5	1: First week, 2: Second week,
				3: Third week
				4: Fourth week, 5: Last week
		end_dotw	0 to 6	0: Sunday to 6: Saturday
		end_hour	0 to 23	0 to 23

Usage example) NTP settings

 $http://192.168.0.10/cgi-bin/time?time_adjust=1&ntp_addr_dhcp=0&ntp_addr=192.168.0.1&ntp_port=123\\ &ntp_interval=12\\ \\$

Usage example) Clock settings

http://192.168.0.10/cgi-bin/date_time?display=0&date_year=2015&date_month=1&date_day=1&date_hour=0&date_min=0&date_sec=0&summer_time=0

4.3. Video over IP Settings

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
JPEG settings	/cgi-bin/set_jpeg	jpeg_quality	0 to 9	0 to 4: High image quality
				5 to 9: Low image quality
		jpeg_quality_	0 to 9	0 to 4: High image quality
		ch2		5 to 9: Low image quality
		jpeg_quality_	0 to 9	0 to 4: High image quality
		ch3		5 to 9: Low image quality
		resol_stream1	320	320: 320 x 180
			640	640: 640 x 360
			1280	1280: 1280 x 720
			1920	1920: 1920 x 1080
		resol_stream2	320	320: 320 x 180
			640	640: 640 x 360
			1280	1280: 1280 x 720
		resol_stream3	320	320: 320 x 180
			640	640: 640 x 360
			1280	1280: 1280 x 720
		jpeg_transmit	0	0: OFF Do not transmit
		1	1	1: ON Transmit
		jpeg_transmit	0	0: OFF Do not transmit
		2	1	1: ON Transmit
		jpeg_transmit	0	0: OFF Do not transmit
		3	1	1: ON Transmit
		jpeg_interval1	5	Frame rate of JPEG(1)
			15(12.5)	5:5 fps
			30(25)	15 (12.5): 15 (12.5) fps
				30 (25): 30 (25) fps
				* The values within () are for the case
				when the system frequency is 50 Hz
		jpeg_interval2	5	Frame rate of JPEG(2)
			15(12.5)	5:5 fps
			30(25)	15 (12.5): 15 (12.5) fps
				30 (25): 30 (25) fps
				* The values within () are for the case
				when the system frequency is 50 Hz
		jpeg_interval3	5	Frame rate of JPEG(3)
			15(12.5)	5:5 fps
			30(25)	15 (12.5): 15 (12.5) fps
				30 (25): 30 (25) fps
				* The values within () are for the case
				when the system frequency is 50 Hz

CGI item name	URL	Parameter name	Parameter value	Description
JPEG stream	/cgi-bin/setdata	LIVESIZE	320	Resolution of JPEG(1)
settings			640	320: 320 x 180
			1280	640: 640 x 360
			1920	1280: 1280 x 720
				1920: 1920 x 1080
		LIVESIZE2	320	Resolution of JPEG(2)
			640	320: 320 x 180
			1280	640: 640 x 360
				1280: 1280 x 720
		LIVESIZE3	320	Resolution of JPEG(3)
			640	320: 320 x 180
			1280	640: 640 x 360
				1280: 1280 x 720
		LIVEQUAL12	0 to 9	Image quality of JPEG(1)
		80		0 to 4: High image quality
				5 to 9: Low image quality
		LIVEQUAL64	0 to 9	Image quality of JPEG(2)
		0		0 to 4: High image quality
				5 to 9: Low image quality
		LIVEQUAL32	0 to 9	Image quality of JPEG(3)
		0		0 to 4: High image quality
				5 to 9: Low image quality
H.264(1) stream	/cgi-bin/set_h264	h264_transmit	0	0: OFF Do not transmit
settings			1	1: ON Transmit
		h264_rtsp_m	0	Internet mode settings
		ode	1	0: OFF
				1: ON
		h264_resoluti	320	320: 320 x 180
		on	640	640: 640 x 360
			1280	1280: 1280 x 720
			1920	1920: 1920 x 1080
			3840(*1)	3840: 3840 x 2160
				(*1): Only for UE70 series
		f_priority	0	0: Fixed bit rate
			1	1: Frame rate priority
			2	2: Best effort transmission
		framerate	5	5: 5 fps
			15(12.5)	15 (12.5): 15 (12.5) fps
			30(25)	30 (25): 30 (25) fps
			60(50)	60 (50): 60 (50) fps
				* The values within () are for the case
				when the system frequency is 50 Hz

CGI item name	URL	Parameter name	Parameter value	Description
		h264_bandwi	512	512:512(kbps)
		dth	768	768:768(kbps)
			1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048:2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)
			32768	32768:32768(kbps)
			40960	40960:40960(kbps)
			51200	51200:51200(kbps)
		h264_bandwi	512	512:512(kbps)
		dth_min	768	768:768(kbps)
		_	1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048:2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)
			24070	24070.24070(NSP3)
				* Can be set when f_priority = 2 (Best
				effort transmission)
			32768	32768:32768(kbps)
			40960	40960:40960(kbps)
			51200	51200:51200(kbps)
		h264_quality	fine	fine: Image quality priority
		11207_quality	low	low: Motion priority
		h264_unimulti	uni	uni: unicast (auto)
		11204_ummull		multi: multicast
			multi	
		uniocat ratif	uni_manual	uni_manual: unicast (manual)
		unicast_port	1024 to 50000	Port number: 1024 to 50000

CGI item name	URL	Parameter name	Parameter value	Description
		unicast_audio	1024 to 50000	Port number: 1024 to 50000
		_port		
		multicast_add	224 to 239	224.0.0.0 - 239.255.255.255
		r1		
		multicast_add	0 to 255	
		r2		
		multicast_add	0 to 255	
		r3		
		multicast_add	0 to 255	
		r4		
		multicast_add	*.*.*.* format	*.*.* format
		r	*.*.*.*.*.*	*:*:*:*:*:*:* format
			format	
		multicast_port	1024 to 50000	1024 to 50000
		multicast_ttl	1 to 254	1 to 254
H.264(2) stream	/cgi-bin/set_h264	h264_transmit	01	0: OFF Do not transmit1: ON
settings	_2			Transmit
		h264_rtsp_m	0	Internet mode settings
		ode	1	0: OFF
				1: ON
		h264_resoluti	320	320:320x180
		on	640	640:640x360
			1280	1280:1280x720
		f_priority	0	0: Fixed bit rate
			1	1: Frame rate priority
			2	2: Best effort transmission
		framerate	5	5: 5 fps
			15 (12.5)	15 (12.5): 15 (12.5) fps
			30 (25)	30 (25): 30 (25) fps
				* The values within () are for the case
				when the system frequency is 50 Hz

CGI item name	URL	Parameter name	Parameter value	Description
		h264_bandwi	512	512:512(kbps)
		dth	768	768:768(kbps)
			1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048: 2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)
		h264_bandwi	512	512:512(kbps)
		dth_min	768	768:768(kbps)
			1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048:2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)
				* Can be set when f_priority = 2 (Best
				effort transmission)
		h264_quality	fine	fine: Image quality priority
			low	low: Motion priority
		h264_unimulti	uni	uni: unicast (auto)
			multi	multi: multicast
			uni_manual	uni_manual: unicast (manual)
		unicast_port	1024 to 50000	Port number: 1024 to 50000
		unicast_audio _port	1024 to 50000	Port number: 1024 to 50000
		multicast_add	224 to 239	224.0.0.0 - 239.255.255.255
		r1		
		multicast_add	0 to 255	
		r2		
		multicast_add	0 to 255	

CGI item name	URL	Parameter name	Parameter value	Description
		r3		
		multicast_add	0 to 255	
		r4		
		multicast_add	*.*.*.* format	*.*.*.* format
		r	*.*.*.*.*.*	*:*:*:*:*:*:* format
			format	
		multicast_port	1024 to 50000	1024 to 50000
		multicast_ttl	1 to 254	1 to 254
H.264(3) stream	/cgi-bin/set_h264	h264_transmit	0	0: OFF Do not transmit
settings	_3		1	1: ON Transmit
		h264_rtsp_m	0	Internet mode settings
		ode	1	0: OFF
				1: ON
		h264_resoluti	320	320:320x180
		on	640	640:640x360
			1280	1280:1280x720
		f_priority	0	0: Fixed bit rate
			1	1: Frame rate priority
			2	2: Best effort transmission
		framerate	5	5: 5 fps
			15 (12.5)	15 (12.5): 15 (12.5) fps
			30 (25)	30 (25): 30 (25) fps
				* The values within () are for the case
				when the system frequency is 50 Hz
		h264_bandwi	512	512:512(kbps)
		dth	768	768:768(kbps)
			1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048:2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)

CGI item name	URL	Parameter name	Parameter value	Description
		h264_bandwi	512	512:512(kbps)
		dth_min	768	768:768(kbps)
		_	1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048:2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)
				* Can be set when f_priority = 2 (Best
				effort transmission)
		h264_quality	fine	fine: Image quality priority
			low	low: Motion priority
		h264_unimulti	uni	uni: unicast (auto)
			multi	multi: multicast
			uni_manual	uni_manual: unicast (manual)
		unicast_port	1024 to 50000	Port number: 1024 to 50000
		unicast_audio _port	1024 to 50000	Port number: 1024 to 50000
		multicast_add r1	224 to 239	224.0.0.0 - 239.255.255.255
		multicast_add	0 to 255	
		r2	0 10 233	
		multicast_add	0 to 255	
		r3	0 10 200	
		multicast_add	0 to 255	
		r4	0 10 200	
		multicast_add	*.*.*.* format	*.*.*.* format
		r	*.*.*.*.*	*:*:*:*:*:*:* format
			format	
		multipoet port		1024 to 50000
		multicast_port	1024 to 50000 1 to 254	1 to 254
☐ 264(4) otroom	/ogi hin/oot h064	multicast_ttl		
H.264(4) stream	/cgi-bin/set_h264	h264_transmit	0	0: OFF Do not transmit 1: ON Transmit
settings	_4	h264 rtcn m		
		h264_rtsp_m	0	Internet mode settings 0: OFF
		ode	1	1: ON
				I. UN

CGI item name	URL	Parameter name	Parameter value	Description
		h264_resoluti	320	320:320x180
		on	640	640:640x360
			1280	1280:1280x720
		f_priority	0	0: Fixed bit rate
			1	1: Frame rate priority
			2	2: Best effort transmission
		framerate	5	5: 5 fps
			15 (12.5)	15 (12.5): 15 (12.5) fps
			30 (25)	30 (25): 30 (25) fps
				* The values within () are for the case
				when the system frequency is 50 Hz
		h264_bandwi	512	512:512(kbps)
		dth	768	768:768(kbps)
			1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048:2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)
		h264_bandwi	512	512:512(kbps)
		dth_min	768	768:768(kbps)
			1024	1024:1024(kbps)
			1536	1536:1536(kbps)
			2048	2048:2048(kbps)
			3072	3072:3072(kbps)
			4096	4096:4096(kbps)
			6144	6144:6144(kbps)
			8192	8192:8192(kbps)
			10240	10240:10240(kbps)
			12288	12288:12288(kbps)
			14336	14336:14336(kbps)
			16384	16384:16384(kbps)
			20480	20480:20480(kbps)
			24576	24576:24576(kbps)
				* Can be set when f_priority = 2 (Best
				effort transmission)
		h264_quality	fine	fine: Image quality priority
			low	low: Motion priority

CGI item name	URL	Parameter name	Parameter value	Description
		h264_unimulti	uni	uni: unicast (auto)
			multi	multi: multicast
			uni_manual	uni_manual: unicast (manual)
		unicast_port	1024 to 50000	Port number: 1024 to 50000
		unicast_audio	1024 to 50000	Port number: 1024 to 50000
		_port		
		multicast_add	224 to 239	224.0.0.0 - 239.255.255.255
		r1		
		multicast_add	0 to 255	
		r2		
		multicast_add	0 to 255	
		r3		
		multicast_add	0 to 255	
		r4		
		multicast_add	* * * *	*.*.* format*:*:*:*:*:* format
		r	format*:*:*:*:*	
			:*:* format	
		multicast_port	1024 to 50000	1024 to 50000
		multicast_ttl	1 to 254	1 to 254
RTSP settings	/cgi-bin/set_rtsp	rtsp_port	1 to 65535	1 to 65535
				* Set to 554 according to factory
		h264 rton m	0	settings
		h264_rtsp_m ode	1	Internet mode settings of H264(1) 0: OFF Do not Transmit
		ode	'	1: ON Transmit
		h264_rtsp_m	0	Internet mode settings of H264(2)
		ode2	1	0: OFF Do not Transmit
		03.02		1: ON Transmit
		h264_rtsp_m	0	Internet mode settings of H264(3)
		ode3	1	0: OFF Do not Transmit
				1: ON Transmit
		h264_rtsp_m	0	Internet mode settings of H264(4)
		ode4	1	0: OFF Do not Transmit
				1: ON Transmit
Live screen initial	/cgi-bin/set_livest	stream	h264	h264:H264(1)
stream selection	art		h264_2	h264_2:H.264(2)
			h264_3	h264_3:H.264(3)
			h264_4	h264_4:H.264(4)
			jpeg	jpeg:JPEG(1)
			jpeg_2	jpeg_2:JPEG(2)
			jpeg_3	jpeg_3:JPEG(3)

Usage example) Change the resolution of H.264(4) to 320 x 180. http://192.168.0.10/cgi-bin/set_h264_4?h264_resolution=320

* This command requires a request by POST.

Usage example) Change the RTSP waiting port at the remote camera side from 554(factory settings) to 555. http://192.168.0.10/cgi-bin/set_rtsp?rtsp_port=555

- * This command requires a request by POST.
- * The h264_rtsp_mode of set_rtsp is a mirror of the WEB menu. RTSP/RTP does not change to TCP even if turned ON.


4.4. Audio Settings

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Audio settings	/cgi-bin/set_audi	audio	off	off: OFF
	0		in	in: ON
			0	0: OFF
			1	1: ON
		audio_encode	aac	Encoder settings AAC (fixed)
		r		
		audio_sens	low	low: Mic Low
			middle	middle: Mic Middle
			high	high: Mic High
			line_low	line_low: Line Low
			line_middle	line_middle: Line Middle
			line_high	line_middle: Line High
		audio_bitrate	64	64: 64 Kbps
			96	96: 96 Kbps
			128	128: 128 Kbps
		audio_alc	0	0: ALC settings OFF
			1	1: ALC settings ON
		plugin_power	0	0: Off
			1	1: On
		audio_transmi	0	0: Off
		t	1	1: On
		equalizer	off	off: Off
			low_cut	low_cut: Low cut
			speech_enhan	speech_enhancement: Audio
			cement	enhancement

Usage example) Turn ON the Audio input signal from the device connected to the AUDIO IN terminal. http://192.168.0.10/cgi-bin/set_audio?audio=1

The control relationship with each parameter is as described below.



4.5. Multi-screen Settings

Method : POST Access level : Admin

Access level . Au				
CGI item name	URL	Parameter	Parameter	Description
NA III a company and the company	to all to too It's a second	name	value	+ + + + f
Multi-screen settings	/cgi-bin/multi_scr	multi_addr1	"*.*.*.*" format	"*.*.*.*" format or
	een	multi_addr2	Or	"*.*.*: 1 to 65535" or
		multi_addr3	"*.*.*.*: 1 to	"String" or
		multi_addr4	65535" or	"String": 1 to 65535"
		multi_addr5	"String" or	
		multi_addr6	"String": 1 to	
		multi_addr7	65535"	
		multi_addr8		
		multi_addr9		
		multi_addr10		
		multi_addr11		
		multi_addr12		
		multi_addr13		
		multi_addr14		
		multi_addr15		
		multi_addr16		
		multi_name1	String (within	Name of the camera
		multi_name2	20 double-byte	
		multi_name3	characters)	
		multi_name4		
		multi_name5		
		multi_name6		
		multi_name7		
		multi_name8		
		multi_name9		
		multi_name10		
		multi_name11		
		multi_name12		
		multi_name13		
		multi_name14		
		multi_name15		
		multi_name16		

Usage example) Set 192.168.0.100/he40 in the first frame.

http://192.168.0.10/cgi-bin/multi_screen?multi_addr1=192.168.0.100&multi_name1=he40

4.6. Priority Stream Settings

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Priority stream	/cgi-bin/set_priori	priority	0	0: Priority stream OFF
settings	ty2		1	1: Priority stream ON
		ip_addr	"*.*.*.*" format	"*.*.*.*" format or
			or	"*:*:*:*:*:*" format
			"*.*.*.*.*.*"	
			format	
		ip_addr2	"*.*.*.*" format	"*.*.*." format or
			or	"*:*:*:*:*:*" format
			"*.*.*.*.*"	
			format	
		stream_type	jpeg	jpeg:JPEG
			jpeg2	jpeg2:JPEG(2)
			jpeg3	jpeg3:JPEG(3)
			h264	h264:H.264(1)
			h264_2	h264_2:H.264(2)
			h264_3	h264_3:H.264(3)
			h264_4	h264_4:H.264(4)

Usage example) The transmission of H264(1) to 192.168.0.99 is implemented on priority. http://192.168.0.10/cgi-bin/set_priority2?priority=1&ip_addr=192.168.0.99&stream_type=h264

4.7. Network Settings

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description								
Network settings	/cgi-bin/network	dhcp	0	0: DHCP OFF (Static settings)								
			1	1: DHCP ON								
		IP_addr1	0 to 255	IP address First octet								
		IP_addr2	0 to 255	IP address Second octet								
		IP_addr3	0 to 255	IP address Third octet								
		IP_addr4	0 to 255	IP address Fourth octet								
		netmask1	0 to 255	Subnet mask First octet								
		netmask2	0 to 255	Subnet mask Second octet								
		netmask3	0 to 255	Subnet mask Third octet								
		netmask4	0 to 255	Subnet mask Fourth octet								
		gateway1	0 to 255	Default gateway First octet								
		gateway2	0 to 255	Default gateway Second octet								
		gateway3	0 to 255	Default gateway Third octet								
		gateway4	0 to 255	Default gateway Fourth octet								
		port	1 to 65535	1 to 65535								
		dns	manual	manual: Manual setting								
			auto	auto: Auto setting								
		pri_server1	0 to 255	Primary server address (DNS) First								
				octet								
		pri_server2	0 to 255	Primary server address (DNS)								
				Second octet								
		pri_server3	0 to 255	Primary server address (DNS) Third octet								
		pri_server4	0 to 255	Primary server address (DNS) Fourth octet								
		sec_server1	0 to 255	Secondary server address (DNS) First octet								
										sec_server2	0 to 255	Secondary server address (DNS) Second octet
		sec_server4	0 to 255	Secondary server address (DNS) Fourth octet								
		ip6_auto	0	IPv6 address manual setting								
		ipo_auto	1	1: off								
			'	0: on								
		in6 addr	*.*.*.*.*.*	IP address								
		ip6_addr	format	IF addless								
			Tomat									

CGI item name	URL	Parameter name	Parameter value	Description
		ip6_gateway	*:*:*:*:*:* format	Default gateway
		ip6_pri_server	*:*:*:*:*:* format	Primary server (IPv6 only)
		ip6_sec_serv er	*:*:*:*:*:* format	Secondary server (IPv6 only)
		ip6_dhcp	0	0: DHCPv6 OFF 1: DHCPv6 ON
		rtp_packet_m ax	1500 1280	RTP packet max. transmission size 1500: Unlimited (1500 byte) 1280: Limited (1280 byte)
		mss	1460 1280 1024	Max. segment size of TCP (MSS) 1460: Unlimited (1460 byte) 1280: Limited (1280 byte) 1024: Limited (1024 byte)
		time	20 unlimited	Effective limit 20: 20 minutes unlimited: Unlimited
		bandwidth	0 64 128	Transmission volume of entire network 0: Unlimited 64:64kbps
			256 384	128:128kbps 256:256kbps
			512 768 1024	384:384kbps 512:512kbps 768:768kbps
			2048 4096	1024:1024kbps 2048:2048kbps
			8192 10000	4096:4096kbps 8192:8192kbps 10000: Unlimited
				* When 10000 is received, an error is not issued, and the operation is performed by assuming "Unlimited".
Easy IP Setup protocol settings	/cgi-bin/easyipset	time	unlimited, 20	Time period during which Easy IP Setup can be performed from the time power is turned ON unlimited: Unlimited 20: 20 minutes

CGI item name	URL	Parameter name	Parameter value	Description
Transmission	/cgi-bin/set_band	bandwidth	0	Transmission volume of entire network
volume of entire	width		1024	0: Unlimited
network			2048	1024:1024kbps
			4096	2048:2048kbps
			8192	4096:4096kbps
			16384	8192:8192kbps
			32768	16384:16384kbps
			10000	32768:32768kbps
				10000: Unlimited
				* When 10000 is received, an error is not issued, and the operation is performed by assuming "Unlimited".
Max. packet length	/cgi-bin/set_rtp	rtp_size	1280	1280: Max. packet length limit
settings			1500	1500: Normal packet length

Usage example) Change the IP address to 192.168.0.30

 $http://192.168.0.10/cgi-bin/network?IP_addr1=192\&IP_addr2=168\&IP_addr3=0\&IP_addr4=30\&netmask \\ 1=255\&netmask2=255\&netmask3=255\&netmask4=128\&gateway1=192\&gateway2=168\&gateway3=0\&gateway4=50 \\$

4.8. UPnP Settings

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
UPnP settings	/cgi-bin/upnp	upnp_portma	0	Auto port-forwarding
		р	1	0: Disabled
				1: Enabled

Usage example) Set UPnP to ON http://192.168.0.10/cgi-bin/upnp?upnp_portmap=1

4.9. Restarting

Method : POST/GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Initialization	/cgi-bin/initial	cmd	reset	Camera restart
		Randomnum	Hexadecimal	16 single-byte character string
			string	

Usage example) Restarting the remote camera http://192.168.0.10/cgi-bin/initial?cmd=reset&Randomnum=12345

44

5. CGI List for Acquisition of Different Types of Information

5.1. Basic Settings Information Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Basic settings	/cgi-bin/get_basi			
information	С			
acquisition				

The response data is as shown below.

cam_title = Camera title
plugin_download = enable/disable
plugin_disp = 0/1

5.2. NTP Settings Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
NTP settings	/cgi-bin/get_time			
information				
acquisition				

The response data is as shown below.

time_adjust = 0/1 ntp_addr_dhcp = 0/1 ntp_addr = String ntp_port = Numeric value (1 to 65535) ntp_interval = Numeric value (1 to 24)

5.3. Clock Settings Information Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Clock settings	/cgi-bin/get_date			
information	_time			
acquisition				

The response data is as shown below.

display = 0/1

date_year = Numeric value

date_month = Numeric value

date_day = Numeric value

date_hour = Numeric value

date_min = Numeric value

date sec = Numeric value

timezone = Numeric value (1 to 74)

 $summer_time = 0/1/2$

start_month = Numeric value

start_week = Numeric value (1 to 5)

start_dotw = Numeric value (0 to 6)

 $start_hour = (0 to 23)$

end_month = Numeric value

end_week = Numeric value (1 to 5)

end_dotw = Numeric value (0 to 6)

end_hour = Numeric value (0 to 23)

is_summer_time = 0/1 (0: OFF, 1: ON)

5.4. Priority Mode Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Priority mode	/cgi-bin/get_priori			
acquisition	ty_mode			

The response data is as shown below.

priority_mode = xxx

^{*} For details on the value notified by xxx, see the parameters of set_priority_mode.

5.5. VideoOverIP Screen Information Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
VideoOverIP screen	/cgi-bin/get_vide			The response is issued in a random
information	o_over_ip			order
acquisition				If transmission to a specific ch is not
				possible due to the specifications,
				the response for the desired ch is not
				returned
				Example) If transmission to h264
				(ch4) is not possible,
				h264_xxxxx_ch4 is not included in
				the response.

The response data is as shown below.

livestart_stream=h264/h264_2/h264_3/h264_4/jpeg/jpeg_2/jpeg_3

jpeg_quality=1/5

jpeg_quality_ch2=1/5

jpeg_quality_ch3=1/5

resol stream1=320/640/1280/1920

resol_stream2=320/640/1280

resol_stream3=320/640/1280

jpeg_transmit1=0/1

jpeg_transmit2=0/1

jpeg_transmit3=0/1

jpeg_interval1=5/15(12.5)/30(25)

jpeg_interval2=5/15(12.5)/30(25)

jpeg_interval3=5/15(12.5)/30(25)

h264_transmit_ch1=0/1

h264_transmit_ch2=0/1

h264_transmit_ch3=0/1

h264_transmit_ch4=0/1

h264_rtsp_mode_ch1=0/1

h264_rtsp_mode_ch2=0/1

h264_rtsp_mode_ch3=0/1

h264_rtsp_mode_ch4=0/1

h264_resolution_ch1=320/640/1280/1920/3840(*1)

h264_resolution_ch2=320/640/1280

h264_resolution_ch3=320/640/1280

h264_resolution_ch4=320/640/1280

h264_f_priority_ch1=0/1/2

h264_f_priority_ch2=0/1/2

h264_f_priority_ch3=0/1/2

```
h264_f_priority_ch4=0/1/2
h264_framerate_ch1=5/15(12.5)/30(25)/60(50)
h264_framerate_ch2=5/15(12.5)/30(25)
h264_framerate_ch3=5/15(12.5)/30(25)
h264 framerate ch4=5/15(12.5)/30(25)
h264 bandwidth ch1 = Numeric value
h264 bandwidth ch2 = Numeric value
h264 bandwidth ch3 = Numeric value
h264_bandwidth_ch4 = Numeric value
h264_bandwidth_min_ch1 = Numeric value
h264_bandwidth_min_ch2 = Numeric value
h264_bandwidth_min_ch3 = Numeric value
h264_bandwidth_min_ch4 = Numeric value
h264_quality_ch1=fine/low1/5
h264_quality_ch2=fine/low1/5
h264_quality_ch3=fine/low1/5
h264_quality_ch4=fine/low1/5
h264_unimulti_ch1=uni/multi/uni_manual
h264_unimulti_ch2=uni/multi/uni_manual
h264 unimulti ch3=uni/multi/uni manual
h264 unimulti ch4=uni/multi/uni manual
h264_unicast_port_ch1 = Numeric value (1024 to 50000)
h264_unicast_port_ch2 = Numeric value (1024 to 50000)
h264 unicast port ch3 = Numeric value (1024 to 50000)
h264_unicast_port_ch4 = Numeric value (1024 to 50000)
h264_unicast_audio_port_ch4 = Numeric value (1024 to 50000)
```

h264_unicast_audio_port_ch1 = Numeric value (1024 to 50000)

h264_unicast_audio_port_ch2 = Numeric value (1024 to 50000)

h264_unicast_audio_port_ch3 = Numeric value (1024 to 50000)

h264_multicast_addr_ch1=xxx.xxx.xxx.xxx

h264_multicast_addr_ch2=xxx.xxx.xxx.xxx

h264 multicast addr ch3=xxx.xxx.xxx.xxx

h264_multicast_addr_ch4=xxx.xxx.xxx.xxx

h264_multicast_port_ch1 = Numeric value (1024 to 50000)

h264 multicast port ch2 = Numeric value (1024 to 50000)

h264_multicast_port_ch3 = Numeric value (1024 to 50000)

h264 multicast port ch4 = Numeric value (1024 to 50000)

h264_multicast_ttl_ch1 = Numeric value (1 to 254)

h264_multicast_ttl_ch2 = Numeric value (1 to 254)

h264 multicast ttl ch3 = Numeric value (1 to 254)

h264_multicast_ttl_ch4 = Numeric value (1 to 254)

(*1): Only for UE70 series

5.6. Audio Settings Information Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Audio settings	/cgi-bin/get_audi			
information	0			
acquisition				

The response data is as shown below.

audio=0/1/off/in audio_sens=low/middle/high/line_low/line_middle/line_high plugin_power=0/1 audio_alc=0/1 equalizer=off/low_cut/speech_enhancement audio_transmit=0/1 audio_bitrate=64/96/128

5.7. Multi-screen Settings Information Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Multi-screen settings	/cgi-bin/get_multi			
information	_screen			
acquisition				

The response data is as shown below.

```
multi_addr1 = "*.*.*." format/"*.*.*.*: 1 to 65535"/"String"/"String": 1 to 65535"
multi_name1 = String (within 20 double-byte characters)
multi_addr2 = "*.*.*.*" format/"*.*.*.*: 1 to 65535"/"String"/"String": 1 to 65535"
multi_name2 = String (within 20 double-byte characters)
multi_addr3 = "*.*.*.*" format/"*.*.*.*: 1 to 65535"/"String"/"String": 1 to 65535"
multi_name3 = String (within 20 double-byte characters)
multi_addr4 = "*.*.*.*" format/"*.*.*.*: 1 to 65535"/"String"/"String": 1 to 65535"

...

multi_addr16 = "*.*.*.*" format/"*.*.*.*: 1 to 65535"/"String"/"String": 1 to 65535"
multi_name16 = String (within 20 double-byte characters)
```

5.8. Host Authentication Settings Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Host authentication	/cgi-bin/get_reg_			
settings information	host			
acquisition				

The response data is as shown below.

```
host = 0/1
host_addr1 = *.*.* format/*.*.*/Mask length format, level = 1/2
host_addr2 = *.*.* format/*.*.*/Mask length format, level = 1/2
host_addr3 = *.*.* format/*.*.*/Mask length format, level = 1/2
host_addr4 = *.*.* format/*.*.*/Mask length format, level = 1/2
host_addr5 = *.*.* format/*.*.*/Mask length format, level = 1/2
host_addr6 = *.*.* format/*.*.*/Mask length format, level = 1/2
host_addr7 = *.*.* format/*.*.*/Mask length format, level = 1/2
```

host_addr8 = *.*.*.* format/*.*.*.*/Mask length format, level = 1/2 host_addr9 = *.*.*.* format/*.*.*.*/Mask length format, level = 1/2

5.9. Priority Stream Settings Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Priority stream	/cgi-bin/get_priori			
settings information	ty			
acquisition				

The response data is as shown below.

```
priority = 0/1

ip_addr = "*.*.*.*" format/"*:*:*:*:*" format

ip_addr2 = "*.*.*.*" format/"*:*:*:*:*:* format

stream_type=jpeg/jpeg2/jpeg3/h264/h264_2/h264_3/h264_4
```

5.10. Network Settings Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Network settings	/cgi-bin/get_netw			
information	ork			
acquisition				

The response data is as shown below.

ip4_dhcp=0/1

ip4_addr=*.*.*.*

ip4_netmask=*.*.*.*

ip4_gateway=*.*.*.*

dns=auto/manual

ip4_pri_server=*.*.*.*

ip4_sec_server=*.*.*.*

ip6_auto=0/1

ip6_addr=*:*:*:*:*:*:

ip6_gateway=*:*:*:*:*:*:

ip6_dhcp=0/1

ip6_pri_server=*:*:*:*:*:

ip6_sec_server=*:*:*:*:*:*:

port = Numeric value (1 to 65535)

rtp_packet_max=1500/1280

mss=1024/1280/1460

bandwidth=0/64/128/256/384/512/768/1024/2048/4096/8192

time=20/unlimited

5.11. UPnP Settings Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
UPnP settings	/cgi-bin/get_upnp			
information				
acquisition				

The response data is as shown below.

 $upnp_portmap = 0/1$

5.12. System Log Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
System log	/cgi-bin/get_syst	type	eventlog	eventlog: Event log
	emlog		errorlog	errorlog: Error log
		num	Numeric value	Acquisition number
			(1 to 100)	
		index	Numeric value	Acquisition start position
			(1 to 100)	

The response data is as shown below.

no\mm/dd/yyyy hh:mm\event code\description\$no\mm/dd/yyyy hh:mm\event code\description\$

•

A "\" is entered between two parameters.

A "\$" is entered between numbers, such as between No. 1 and No. 2.

^{*} No line feed.

5.13. Camera Status Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Camera status	/cgi-bin/get_stat			rec: Is recording in progress or not
acquisition	е			rec_counter: Recording elapsed time
				ftp_send: Is FTP transfer in progress or not
				play: Is playback in progress or not
				del_file: Is file deletion in progress or not
				download: Is download in progress or not
				sd_format: Is SD card formatting in progress
				or not
				sd_insert: Has SD card been inserted or not
				sd_repair: Is SD card being repaired or not
				sd_error: Is SD card in error state or not
				sd_rem: SD card remaining amount [Gbyte]
				sd_org: SD cad capacity [Gbyte]

The response data is as shown below.

rec=on/off

rec_counter=hh:mm:ss

ftp_send=on/off

play=on/off

del_file=on/off

download=on/off

sd_format=on/off

sd_insert=on/off

sd_repair=on/off

sd_error=on/off

sd_rem = xx/ ---- (xx: Remaining amount [Gbyte])

sd_org = yy/ ---- (yy: Capacity [Gbyte])

5.14. UPnP Execution Results Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Status acquisition	/cgi-bin/get_statu	-	-	UPnP execution result

The response data is as shown below.

http_port = Numeric value http_status = enable/disable https_port = Numeric value https_status = enable/disable addr = String

5.15. Preset Position Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Preset position	/cgi-bin/get_prep	command	list	list: Preset position registration status
information	osi			acquisition
acquisition				

The response data is as shown below.

PRESET_POSITION_REGISTRATION = String

HOME = 0

 $POSI1_ID = xxx$

 $POSI2_ID = xxx$

•

•

POSI100ID = xxx

5.16. Other Setting Values Acquisition

Method : GET Access level : Admin

acquisition CGI value to be acquir img_mode Imaging mode imgratio Image ratio img_fps Frame rate livestream Live screen initial liveint liveint JPEG(1) re livequalbase livequalbase JPEG(1) livequal livequal JPEG(1) livequal livequal JPEG(1) livesize livesize: JPEG(2) livesize2 livesize: JPEG(2) livesize3 livequal: JPEG(3) livequal2 livequal: JPEG(3) livequal3 livequal4 JPEG(3) livequal4 livequal5 JPEG(3) livequal6 linternet mode (H.) ON/OFF h264bwc Bit rate per client transmission don h264rtspmode Bit rate per client transmission don h264bwcmin H.264(1) Bit rate (minimum) h264rtspmode_2 (H.264 transmission h264rtspmode_3 h264rtspmode_3 h264rtspmode_3 h264rtspmode_4 h264r	CGI item name	URL	Parameter name	Parameter value	Description
img_mode Imaging mode imgratio Image ratio Image ratio img_fps Frame rate livestream Live screen initial liveint liveint: JPEG(1) re livequalbase: JP image quality livesize livesize: JPEG(1) livequal livequal: JPEG(1) livesize2 livesize: JPEG(2) livesize3 livesize3 livesize3 livesize4 livesize5 JPEG(2) livequal JPEG(2) livequal JPEG(3) livequal: JPEG(3) livequal: JPEG(3) livequal JPEG(4) livesize JPE	•	/cgi-bin/getdata	req	-	Specify the item name of the setting
imgratio Image ratio img_fps Frame rate livestream Live screen initial liveint liveint JPEG(1) re livequalbase: JP image quality livesize livesize: JPEG(1) livesize livesize: JPEG(1) livesize2 livesize: JPEG(2) livequal2 livequal: JPEG(2) livesize3 livesize: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client nrh264bwc Bit rate per client ransmission doe h264bwcmin H.264(1) Bit rate per client livesize3 livesize3 h264rtspmode_2: (H.264 transmissish h264rtspmode_3 h264rtspmode_3: (H.264 transmissish h264rtspmode_4 h264rtspmode_4: (H.264 transmissish h264rtspmode_4: (H.264 transmis	acquisition CGI				·
img_fps					
livestream Live screen initial liveint: JPEG(1) re livequalbase livequalbase: JPEG(1) re livequalbase: JPEG(1) livesize: JPEG(1) livesize: JPEG(1) livesize: JPEG(2) livequal: JPEG(2) livesize: JPEG(2) livequal: JPEG(2) livequal: JPEG(3) livesize3 livesize: JPEG(3) livesize3 livesize: JPEG(3) livequal3 livequal: JPEG(3) livequal3 livequal: JPEG(3) livequal3 livequal4 livequal5 livequal6 lnternet mode (H. ON/OFF h264bwc Bit rate per client rnh264bwc Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate per client transmission dod h264rtspmode_2 h264rtspmode_2: (H.264 transmissi h264rtspmode_3) h264rtspmode_3: (H.264 transmissi h264rtspmode_4: (H.264 transmissi h264rtspmode_4: (H.264 transmissi rtspport rtspport: RTSP se h264size h.264size: h.264 race h.264qual: h.264 rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264mtd: h.264mtd method					<u> </u>
liveint liveint: JPEG(1) re livequalbase: JP image quality livesize livesize: JPEG(1) livequal livequal: JPEG(1) livesize2 livesize: JPEG(2) livesize3 livesize: JPEG(2) livesize3 livesize: JPEG(3) livequal2 livesize: JPEG(3) livequal3 livequal: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client atransmission dod h264bwcmin H.264(1) Bit rate per client atransmission dod h264bwcmin H.264(1) Bit rate per client atransmission dod h264rtspmode_2 (H.264 transmission dode) h264rtspmode_3 h264rtspmode_3: (H.264 transmission h264rtspmode_4: (H.264 transmission h264rtspm				<u> </u>	Frame rate
livequalbase livequalbase: JP image quality livesize livesize: JPEG(1) livequal livequal: JPEG(1) livesize2 livesize: JPEG(2) livesize3 livesize: JPEG(3) livequal3 livequal: JPEG(3) livequal3 livequal: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate per client transmission dod h264rtspmode_2 h264rtspmode_2: (H.264 transmission dode) h264rtspmode_3 h264rtspmode_3: (H.264 transmission dode) h264rtspmode_4 h264rtspmode_4: (H.264 transmission dode) h264rtspmode_4 h264rtspmode_3: (H.264 transmissi				livestream	Live screen initial stream selection
image quality livesize livesize: JPEG(1) livequal livequal: JPEG(2) livesize2 livesize: JPEG(2) livesize3 livesize: JPEG(3) livequal3 livequal: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode lnternet mode (H.: ON/OFF h264bwc Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate per client transmission dod h264rtspmode_2 h264rtspmode_2: (H.264 transmissii h264rtspmode_3 h264rtspmode_3: (H.264 transmissii h264rtspmode_4 h264rtspmode_4: (H.264 transmissii rtspport rtspport: RTSP se h264size h.264size: h.264 r h264qual h.264qual: h.264 in.264 t h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 t method				liveint	liveint: JPEG(1) refresh interval
livesize livesize: JPEG(1) livequal livequal: JPEG(1) livequal livequal: JPEG(2) livesize2 livesize: JPEG(2) livequal2 livequal: JPEG(3) livequal3 livequal: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client transmission doo h264bwcmin H.264(1) Bit rate per client transmission doo h264rtspmode_2 (H.264 transmissis h264rtspmode_3 h264rtspmode_3 h264rtspmode_3 (H.264 transmissis h264rtspmode_4 h264rtspmode_4 (H.264 transmissis tspport tspport: RTSP se h264size h.264size: h.264 h264qual h.264qual: h.264 h264rint h.264rint: Refresh cycle) h264mtd h.264mtd h.264mtd: h.264 transmissis h264mtd h.264mtd: h.264 transmissis h264mtd: h.264mtd h.264mtd: h.264 transmissis h264mtd: h.264mtd: h.264mtd h.264mtd: h.264 transmissis h264mtd: h.264mtd: h.26				livequalbase	livequalbase: JPEG(1) default
livequal livequal: JPEG(1) livesize2 livesize: JPEG(2) livequal2 livequal: JPEG(2) livequal3 livequal: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client rrh264bwc Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate per client (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmission h264rtspmode_3 h264rtspmode_3: (H.264 transmission h264rtspmode_4 h264rtspmode_4: (H.264 transmission h264rtspmode_4 h264rtspmode_4: (H.264 transmission h264rtspmode_4 h264rtspmode_4: (H.264 transmission h264rtspmode_4: (H.264 tr				line at a	<u> </u>
livesize2 livesize: JPEG(2) livequal2 livequal: JPEG(2) livesize3 livesize: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client nrh264bwc Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate p (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmissi h264rtspmode_3 h264rtspmode_3: (H.264 transmissi h264rtspmode_4 h264rtspmode_4: (H.264 transmissi rtspport rtspport: RTSP se h264size h.264size: h.264 r h264qual h.264qual: h.264 i h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 tr					livesize: JPEG(1) image resolution
livequal2 livequal: JPEG(2) livesize3 livesize: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client nrh264bwc Bit rate per client transmission dod h264bwcmin H.264(1) Bit rate per client (minimum) h264rtspmode_2 (H.264 transmission h264rtspmode_3 h264rtspmode_2: (H.264 transmission h264rtspmode_4 h264rtspmode_3: (H.264 transmission h264rtspmode_4 h264rtspmode_4: h264rtspmode_5 h264rtspmode_6 h264rts				· · · · · · · · · · · · · · · · · · ·	livequal: JPEG(1) image quality
livesize3 livesize: JPEG(3) livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client nrh264bwc Bit rate per client transmission doc h264bwcmin H.264(1) Bit rate p (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmissis h264rtspmode_3 h264rtspmode_3: (H.264 transmissis h264rtspmode_4 h264rtspmode_4: (H.264 transmissis rtspport rtspport: RTSP se h264size h.264size: h.264 i h264qual h.264qual: h.264 i h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 transmissi					livesize: JPEG(2) image resolution
livequal3 livequal: JPEG(3) h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client nrh264bwc Bit rate per client transmission doe h264bwcmin H.264(1) Bit rate per client (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmissi h264rtspmode_3 h264rtspmode_3: (H.264 transmissi h264rtspmode_4 h264rtspmode_4: (H.264 transmissi rtspport rtspport: RTSP se h264size h.264size: h.264 i h264qual h.264qual: h.264 i h264rint h.264rtit: Refresh cycle) h264mtd h.264mtd: h.264 tr				· · · · · · · · · · · · · · · · · · ·	livequal: JPEG(2) image quality
h264 H264(1) transmiss h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client a transmission dod h264bwcmin H.264(1) Bit rate per (minimum) h264rtspmode_2 (H.264 transmission h264rtspmode_3: (H.264 transmission h264rtspmode_4: (H.264					livesize: JPEG(3) image resolution
h264rtspmode Internet mode (H.: ON/OFF h264bwc Bit rate per client nrh264bwc Bit rate per client at transmission doe h264bwcmin H.264(1) Bit rate per (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmission h264rtspmode_3 h264rtspmode_3: (H.264 transmission h264rtspmode_4 h264rtspmode_4: (H.264 transmission rtspport rtspport: RTSP see h264size h.264size: h.264 is h264rint h.264qual: h.264 is h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 transmission rtspoort rtspport: RTSP see h264size h.264size: h.264 is h264rint h.264rint: Refresh cycle)				livequal3	livequal: JPEG(3) image quality
ON/OFF h264bwc Bit rate per client transmission doe h264bwcmin H.264(1) Bit rate per (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmission h264rtspmode_3: (H.264 transmission h264rtspmode_4 h264rtspmode_4: (H.264 transmission h264rtspmode_4 h264rtspmode_4: (H.264 transmission h264rtspmode_4: (H.264 transmission h264rtspmode_4: (H.264 transmission h264size h264size: h.264size: h.264siz				h264	H264(1) transmission ON/OFF
h264bwc Bit rate per client transmission doe h264bwcmin H.264(1) Bit rate per (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmission h264rtspmode_3: (H.264 transmission h264rtspmode_4 transmission h264rtspmode_4. h264rtspmode_4 h264rtspmode_4: (H.264 transmission h264rtspmode_4.) rtspport rtspport: RTSP see h264size h.264size: h.264 rate h264qual h.264qual: h.264qual: h.264 rate h264qual h.264qual: h.264qual				h264rtspmode	Internet mode (H.264 transmission 1)
nrh264bwc Bit rate per client a transmission doe h264bwcmin H.264(1) Bit rate per (minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmission h264rtspmode_3) h264rtspmode_3 (H.264 transmission h264rtspmode_4) h264rtspmode_4: (H.264 transmission h264rtspmode_4) h264rtspmode_4: (H.264 transmission rtspport rtspport: RTSP see h264size h.264size: h.264 in h264qual h.264qual: h.264 in h264qual h.264qual: h.264 in h264rint h264rint: Refresh cycle) h264mtd h.264mtd: h.264 to method				h264hwc	
transmission doe h264bwcmin H.264(1) Bit rate p (minimum) h264rtspmode_2 (H.264 transmissie h264rtspmode_3 (H.264 transmissie h264rtspmode_4 h264rtspmode_4 (H.264 transmissie rtspport rtspport rtspport: RTSP se h264size h.264size: h.264 r h264qual h.264qual: h.264 int: Refresh cycle) h264mtd h.264mtd: h.264 tr					·
h264bwcmin				1111204bWC	transmission does not stop
(minimum) h264rtspmode_2 h264rtspmode_2: (H.264 transmissis h264rtspmode_3 h264rtspmode_3: (H.264 transmissis h264rtspmode_4 h264rtspmode_4: (H.264 transmissis rtspport rtspport: RTSP se h264size h.264size: h.264 r h264qual h.264qual: h.264 i h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 transmissis rtspport h264mtd h.264mtd: h.264 transmissis rtspport h264qual h.264qual: h.264 i h264qual h.264qual: h.264 i h264rint h.264mtd: h.264 transmissis rtspport h264mtd h.264mtd h.2				h264bwcmin	H.264(1) Bit rate per client
(H.264 transmission h264rtspmode_3: h264rtspmode_4 h264rtspmode_4: (H.264 transmission rtspport rtspport: RTSP set h264size h.264size: h.264 respective h264qual h.264qual: h.26					
h264rtspmode_3 h264rtspmode_3:				h264rtspmode_2	h264rtspmode_2: Internet mode
(H.264 transmission h264rtspmode_4:					(H.264 transmission 2) ON/OFF
h264rtspmode_4:				h264rtspmode_3	h264rtspmode_3: Internet mode
rtspport rtspport: RTSP se h264size h.264size: h.264 r h264qual h.264qual: h.264 i h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 ti method					(H.264 transmission 3) ON/OFF
rtspport rtspport: RTSP se h264size h.264size: h.264 rt h264qual h.264qual: h.264 i h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 tt method				h264rtspmode_4	h264rtspmode_4: Internet mode
h264size h.264size: h.264 results h264qual h.264qual: h.264 in h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 te method					(H.264 transmission 4) ON/OFF
h264qual h.264qual: h.264 i h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 ti method				rtspport	rtspport: RTSP server port number
h264rint h.264rint: Refresh cycle) h264mtd h.264mtd: h.264 ti method				h264size	h.264size: h.264 resolution
h264mtd h.264mtd: h.264 to method				h264qual	h.264qual: h.264 image quality
h264mtd h.264mtd: h.264 to method				h264rint	h.264rint: Refresh cycle (I frame
method					, ,
				h264mtd	h.264mtd: h.264 transmission
				1004 1 111	
				h264mladd1	h.264mladd1: h.264 multicast
				h264mladd2	address First octet h.264mladd2: h.264 multicast

CGI item name	URL	Parameter name	Parameter value	Description
				address Second octet
			h264mladd3	h.264mladd3: h.264 multicast
				address Third octet
			h264mladd4	h.264mladd4: h.264 multicast
				address Fourth octet
			h264mlport	h.264mlport: h.264 multicast
				transmission destination port number
			h264mlttl	h.264mlttl: h.264 multicast TTL
			h264uniport	h.264uniport: Unicast (for video) port
				number
			h264uniport2	h.264uniport2: Unicast (for audio)
				port number
			h264profile	H.264 profile
			h264codind	H.264 encoding system
			h264_2	h.264_2: h.264 transmission
				ON/OFF 2
			h264bwc_2	h.264bwc_2: Bit rate per client 2
			h264size_2	h.264size_2: h.264 resolution 2
			h264qual_2	h.264qual_2: h.264 image quality 2
			h264rint_2	h.264rint_2: Refresh cycle (I frame
				cycle) 2
			h264mtd_2	h.264mtd: h.264 transmission
				method 2
			h264mladd1_2	h.264mladd1_2: h.264 multicast
				address First octet 2
			h264mladd2_2	h.264mladd2_2: h.264 multicast
				address Second octet 2
			h264mladd3_2	h.264mladd3_2: h264 multicast
				address Third octet 2
			h264mladd4_2	h.264mladd4_2: h264 multicast
				address Fourth octet 2
			h264mlport_2	h.264mlport_2: h264 multicast
				transmission destination port number 2
			h264mlttl_2	h264mlttl_2: h264 multicast TTL2
			h.264uniport_2	h.264uniport_2: Unicast (for video)
			1.004	port number 2
			h264uniport2_2	h.264uniport2_2: Unicast (for audio) port number 2
			h264profile_2	H.264 profile 2
			h264codind_2	H.264 encoding system 2
			h264_3	h.264_2: h.264 transmission

CGI item name	URL	Parameter name	Parameter value	Description
				ON/OFF 3
			h264bwc_3	h.264bwc_3: Bit rate per client 3
			h264size_3	h.264size_3: h.264 resolution 3
			h264qual_3	h.264qual_3: h.264 image quality 3
			h264rint_3	h.264rint_3: Refresh cycle (I frame
				cycle) 3
			h264mtd_3	h.264mtd_3: h.264 transmission
			1004 1 114 0	method 3
			h264mladd1_3	h.264mladd1_3: h.264 multicast
			b 00 4 m la dal0 0	address First octet 3
			h264mladd2_3	h.264mladd2_3: h.264 multicast
			h 20 4 m lo d d 2 2	address Second octet 3
			h264mladd3_3	h.264mladd3_3: h264 multicast address Third octet 3
			h264mladd4_3	h.264mladd4_3: h264 multicast
			112041111auu4_3	address Fourth octet 3
			h264mlport_3	h.264mlport_3: h264 multicast
			1120 1111port_0	transmission destination port number
				3
			h264mlttl_3	h264mlttl_3: h264 multicast TTL3
			h.264uniport_3	h.264uniport_3: Unicast (for video)
				port number 3
			h264uniport2_3	h.264uniport2_3: Unicast (for audio)
				port number 3
			h264profile_3	H.264 profile 3
			h264codind_3	H.264 encoding system 3
			h264_4	h.264_4: h.264 transmission
				ON/OFF 4
			h264bwc_4	h.264bwc_4: Bit rate per client 4
			h264size_4	h.264size_4: h.264 resolution 4
			h264qual_4	h.264qual_4: h.264 image quality 4
			h264rint_4	h.264rint_4: Refresh cycle (I frame
				cycle) 4
			h264mtd_4	h.264mtd_4: h.264 transmission
				method 4
			h264mladd1_4	h.264mladd1_4: h.264 multicast
			h 00 4 malo el -10 4	address First octet 4
			h264mladd2_4	h.264mladd2_4: h.264 multicast address Second octet 4
			h264mladd2 4	
			h264mladd3_4	h.264mladd3_4: h264 multicast address Third octet 4
			h264mladd4_4	h.264mladd4_4: h264 multicast
				address Fourth octet 4
	<u> </u>		l .	

CGI item name	URL	Parameter name	Parameter value	Description
			h264mlport_4	h264mlport_4: h264 multicast
				transmission destination port number
				4
			h264mlttl_4	h264mlttl_4: h264 multicast TTL4
			h.264uniport_4	h.264uniport_4: Unicast (for video)
				port number 4
			h264uniport2_4	h.264uniport2_4: Unicast (for audio)
				port number 4
			h264profile_4	H.264 profile 4
			h264codind_4	H.264 encoding system 4
			h264mlauto	H264(1) multicast auto start
			h264mlauto_2	H264(2) multicast auto start
			h264mlauto_3	H264(3) multicast auto start
			h264mlauto_4	H264(4) multicast auto start
			audio_level	audio_level: Audio authorization and
				authentication level setting
			audio_sens	audio_sens: Sound collection
				sensitivity
			nrlivequal	nrlivequal: JPEG image quality at
				which transmission does not stop
			nrh264size	nrh264size: H.264 resolution at
				which transmission does not stop
			nrh264qual	nrh264qual: H.264 image quality at
				which transmission does not stop
			nrh264bwc_2	nrh264bwc_2: Bit rate per client 2 at
				which transmission does not stop
			nrh264size_2	nrh264size_2: H.264 resolution 2 at
				which transmission does not stop
			nrh264qual_2	nrh264qual_2: H.264 image quality 2
			1.0041	at which transmission does not stop
			nrh264bwc_3	nrh264bwc_3: Bit rate per client 3 at
				which transmission does not stop
			nrh264size_3	nrh264size_3: H.264 resolution 3 at
			prh264gual 2	which transmission does not stop
			nrh264qual_3	nrh264qual_3: H.264 image quality 3 at which transmission does not stop
			nrh264bwc_4	nrh264bwc_4: Bit rate per client 4 at
			11112040W6_4	which transmission does not stop
			nrh264size_4	nrh264size_4: H.264 resolution 4 at
			20 10120_7	which transmission does not stop
			nrh264qual_4	nrh264qual_4: H.264 image quality 4
			5 /9661_ /	at which transmission does not stop
			h264fpriority	h264fpriority: H.264(1) transmission
				mode
L	<u> </u>		1	<u>I</u>

CGI item name	URL	Parameter name	Parameter value	Description
			h264nrframerate	h264nrframerate: H.264(1) frame
				rate
			h264fpriority_2	h264fpriority_2: H.264(2)
				transmission mode
			h264nrframerate_2	h264nrframerate_2: H.264(2) frame rate
			h264fpriority_3	h264fpriority_3: H.264(3) transmission mode
			h264nrframerate_3	h264nrframerate_3: H.264(3) frame rate
			h264fpriority_4	h264fpriority_4: H.264(4)
				transmission mode
			h264nrframerate_4	h264nrframerate_4: H.264(4) frame
				rate
			h264bwcmin_2	H.264(2) Bit rate per client
				(minimum)
			h264bwcmin_3	H.264(3) Bit rate per client
				(minimum)
			h264bwcmin_4	H.264(4) Bit rate per client
				(minimum)
			livequalbase	JPEG default image quality
			liveframerate	Live screen initial frame rate (JPEG)
			plugin_halftone_jp	Enabling/disabling of half-tone
			eg	function for JPEG images in Active X
			plugin_halftone_h2	Enabling/disabling of half-tone
		(h) \	64	function for H.264 movies in Active X
		(None)	-	If there is no parameter specification,
				issue the list of setting data in a
				batch, as the response.

For details, see "Acquiring the List of Setting Values".

6. CGI List for HTTPS Control

6.1. Setting Information and Acquiring Certification

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
HTTPS self-signed	https_self_signe	mode	get_info	get_info: Information confirmation
certificate	d		delete	delete: Delete
HTTPS CA	https_signed	mode	get_info	get_info: Information confirmation
certificate			delete	delete: Delete
HTTPS CRT key	https_crt_key	mode	refresh	Processing of CRT key
history usage				refresh: Update
HTTPS connection	set_https	live	http	http: HTTP
method			https	https: HTTPS
		https_port	1 to 65535	HTTPS port number
HTTPS self-signed	https_creat_self_	common_nam	String	Host name
certificate generate	signed	е		
		country	String	Country name
		state	String	Prefecture name
		locality	String	Locality name
		organization	String	Organization name
		organization_	String	Department name
		unit		
HTTPS CSR	https_creat_sign	common_nam	String	Host name
generate	ed	е		
		country	String	Country name
		state	String	Prefecture name
		locality	String	Locality name
		organization	String	Organization name
		organization_	String	Department name
		unit		
HTTPS CSR	/cgi-bin/https_do			
download	wnload_csr			
HTTPS CA	https_install_sign	-	-	-
certificate install	ed			
HTTPS CRT key	https_change_crt	rsa_length	1024	1024: 1024 bit
generate	_key		2048	2048: 2048 bit

CGI item name	URL	Parameter name	Parameter value	Description
Status update	renewal	cgi_name	self_create	self_create: Self-signed certificate
				creation status
			csr_create	csr_create: CSR creation status
			ca_install	ca_install: CA certificate installation
				status
			key_create	key_create: CRT key generation
				status

6.2. Information Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
HTTPS settings	/cgi-bin/get_https			
information				
acquisition				
HTTPS CRT key	/cgi-bin/get_crt_k			
information	еу			
acquisition				

It is recommended to implement the HTTPS settings through GUI from the WEB menu. Some models may not have the HTTPS function.

61

7. CGI List for FTP Control

7.1. FTP Server Settings

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
FTP server settings	/cgi-bin/set_ftp	server_addr	*.*.*.* format,	*.*.* format, string
			string	*:*:*:*:*:*:* format
			..*.*.*.*	(within 128 single-byte alphanumeric
			format	characters)
		username	String	String
				(within 32 single-byte alphanumeric
				characters)
		password	String	String
				(within 32 single-byte alphanumeric
				characters)
		port_num	1 to 65535	1 to 65535
		mode	active	active: Active mode
			passive	passive: Passive mode
		dirname	String	Folder name created in the root
				directory of the user after logging in
				to the FTP server (String (within 256
				characters))
				* Characters that can be entered:
				Double-byte, single-byte symbols (",
				&, :)

Usage example) Set the FTP server "192.168.0.1". Set the ID/PASS of the FTP server as user1/password, and the folder as user1.

http://192.168.0.10/cgi-bin/set_ftp?server_addr=192.168.0.1&username=user1&password=password&port_num=100&mode=active&dirname=dir

7.2. FTP Server Transfer Instruction

Method : POST/GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Transfer to FTP	/cgi-bin/send_ftp	fileno	Numeric value	File No. acquired by
server	server			/cgi-bin/get_mp4_list2
				* Up to 50 file numbers can be
				specified
				When specifying multiple files,
				separate the File No. with a ",".
		select_type	fileno	fileno: File No.
			all	all: Specify all
				* When "all" is specified, do not
				specify the File No. to be transferred.
		list_id	Numeric value	List ID acquired by
				/cgi-bin/get_mp4_list2
Cancellation of	/cgi-bin/cancel_s			
transfer to FTP	end_ftpserver			
server				

Usage example) Transfer File No. 1 by specifying the file no. http://192.168.0.10/cgi-bin/send_ftpserver?fileno=1&select_type=fileno&list_id=100

Usage example) Transfer File No. 1 and No. 3 by specifying the file no. http://192.168.0.10/cgi-bin/send_ftpserver?fileno=2,3&select_type=fileno&list_id=100

Usage example) Transfer all files http://192.168.0.10/cgi-bin/send_ftpserver?select_type=all&list_id=100

Usage example) Cancel transfer http://192.168.0.10/cgi-bin/cancel_send_ftpserver

7.3. FTP Server Information Acquisition

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
FTP server settings	/cgi-bin/get_ftp			
information				
acquisition				

The response data is as shown below.

mode = active/passive

server_addr = *.*.* format/*:*:*:*:*:* format
dirname = String
username = String
port_num = Numeric value

7.4. FTP Server Progress Confirmation

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Progress	/cgi-bin/get_prog	type	send_ftp	Acquisition of progress of FTP server
confirmation	ress			transfer

The response data is as shown below.

progress = xxx rate = Numeric value (%)


* Value to be entered in xxx

prepare: Preparation in progress exec: Processing in progress

finish: Completed


cancel: Cancellation in progress error: Termination with an error * "rate" indicates the rate of progress.

7.5. FTP Control Sequence



7.6. About Folder Settings at the FTP Server Side

In the remote camera, a predetermined folder is created inside the transfer-destination FTP server each time a transfer start command (/cgi-bin/send_ftpserver) is issued to the FTP server, and the MP4 files within the SD card are transferred.



If the designated folder (dirname according to FTP server settings) to be set at the remote camera side does not exist at the FTP server side, the remote camera automatically creates a new folder when transfer starts**. In addition, a sequence number folder starting with "AW" is created under the designated folder, and an SD card folder image starting with DCIM is transferred to the folder.

If a sequence number folder starting with "AW" exists at the time of start of transfer, a new folder with the numeric value incremented by one is created automatically.

Note that if the AW999999 folder exists, FTP transfer cannot be started.

**note

If FTP transfer fails, the designated folder (dirname in FTP server settings) to be set on the remote camera side may not exist. We recommend creating the folder in advance on the FTP server side.

8. CGI List for Recording/Playback Control on SD Card

8.1. Video Recording Mode Settings

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
SD card recording	/cgi-bin/set_sdre	mode	1080_60p_28	1080_60p_28m:1920x1080/60p
mode settings	c_mode		m	28Mbps
			1080_30p_15	1080_30p_15m:1920x1080/30p
			m	15Mbps
			1080_30p_10	1080_30p_10m:1920x1080/30p
			m	10Mbps
			1080_30p_6m	1080_30p_6m:1920x1080/30p
				6Mbps
			720_60p_15m	720_60p_15m:1280x720/60p
			720_30p_8m	15Mbps
			720_30p_4m	720_30p_8m:1280x720/30p 8Mbps
			720_30p_2m	720_30p_4m:1280x720/30p 4Mbps
				720_30p_2m:1280x720/30p 2Mbps
			1080_50p_28	1080_50p_28m:1920x1080/50p
			m	28Mbps
			1080_25p_15	1080_25p_15m:1920x1080/25p
			m	15Mbps
			1080_25p_10	1080_25p_10m:1920x1080/25p
			m	10Mbps
			1080_25p_6m	1080_25p_6m:1920x1080/25p
				6Mbps
			720_50p_15m	720_50p_15m:1280x720/50p
				15Mbps
			720_25p_8m	720_25p_8m:1280x720/25p 8Mbps
			720_25p_4m	720_25p_4m:1280x720/25p 4Mbps
			720_25p_2m	720_25p_2m:1280x720/25p 2Mbps
			2160_30p_72	2160_30p_72m:3840x2160/30p
			m(*1)	72Mbps
			2160_25p_72	2160_25p_72m:3840x2160/25p
			m(*1)	72Mbps
				(*1): Only for UE70 series
REC link tally	/cgi-bin/set_recta	enable	true	true: Linking ON
settings	lly		false	false: Linking OFF

Usage example) Set to 1080/30p_15 Mbps http://192.168.0.10/cgi-bin/set_sdrec_mode?mode=1080_30p_15m

8.2. Video Recording Mode Acquisition

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
SD card recording	/cgi-bin/get_sdre			
mode acquisition	c_mode			
REC link tally	/cgi-bin/get_recta			
settings acquisition	lly			

The response data is as shown below.

 $sdrec_mode = xxx$

8.3. Video Recording Start/End Control

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
MP4 recording to SD	/cgi-bin/sdctrl	save	start	start: Recording start
card			end	end: Recording end

Usage example) Start MP4 recording to the SD card.

http://192.168.0.10/cgi-bin/sdctrl?save=start

Usage example) End MP4 recording to the SD card.

http://192.168.0.10/cgi-bin/sdctrl?save=end

^{*} For details on the value notified by xxx, see the parameters of /cgi-bin/set_sdrec_mode.

^{*} Both recording start and recording end require a few seconds as processing time. Secure some interval time during operation.

8.4. SD Card Format (Initialization) Control

Method : POST Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
SD card format	/cgi-bin/sdcard	cmd	format	Formatting of SD memory card

Usage example) Start formatting (initialization) of SD card http://192.168.0.10/cgi-bin/sdcard?cmd=format

- * If you perform formatting during the use of the SD card, "ErrorNo=3" is returned in the main text. You cannot perform formatting in such a case.
- * Depending on the type and state of the card, formatting (initialization) of the SD card may be performed after complete erasure of the SD card. In such a case, a maximum of approx. 120 seconds are needed as the processing time./ Issue the next command after confirming completion of formatting with cgi-bin/get_progress.

8.5. SD Card Format (Initialization) Progress Confirmation

Method : GET Access level : Admin

CGI item name	URL	Parameter name	Parameter value	Description
Progress	/cgi-bin/get_prog	type	format	Acquisition of formatting progress of
confirmation	ress			SD memory card

The response data is as shown below.

progress = xxx

* Value to be entered in xxx

prepare: Preparation in progress exec: Processing in progress

finish: Completed

cancel: Cancellation in progress error: Termination with an error

8.6. MP4 File List Search

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
MP4 list search of	/cgi-bin/get_mp4	maxmatches	1 to 15	Upper-limit of number of lists to be
SD card	_list2			acquired
				* Can be omitted
		index	Numeric value	List search start position
				1 to 65535

Usage example) Acquire list from No. 1 with 10 as the upper-limit number. http://192.168.0.10/cgi-bin/get_mp4_list2?maxmatches=10&index=1

The response data is as shown below.

no,filename,mm/dd/yyyy hh:mm:ss,duration[CR][LF]

.

MP4fileNum = Numeric value (acquired number of lists) [CR][LF] MP4fileALLNum = Numeric value (total number of files) [CR][LF] list id = Numeric value

The response data example is as shown below.

no,filename,mm/dd/yyyy hh:mm:ss,duration[CR][LF]
1,S0MA001000000110,01/01/2015 12:0:0,00:05:05[CR][LF]
2,S0MA001000000210,01/01/2015 15:15:15,00:05:05[CR][LF]
MP4fileNum=2[CR][LF]
MP4fileALLNum=2[CR][LF]
list id=123

Note that mm/dd/yyyy hh:mm:ss and duration indicate the recording start date and time and recording elapsed time of the corresponding MP4 file.

list_id on the last line is a unique value for the acquired file list. It is used for deletion, download, and FTP transfer.

8.7. MP4 File Playback Control

Method : GET Access level : Live

CGI item name	URL	Parameter	Parameter	Description
		name	value	
Selection of playback	/cgi-bin/set_plays	filename	String	File name acquired by
data	cene_mp4			/cgi-bin/get_mp4_list2
		list_id	Numeric value	List ID acquired by
				/cgi-bin/get_mp4_list2
Playback of stored	/cgi-bin/playcmd	type	start	start: Playback from the start position
data	_mp4		stop	stop: Playback stopped
			pause	pause: Playback paused
			restart	restart: Playback resumed
		restart_msec	Numeric value	Number of seconds (msec) from the
				start position
				* Specified when type = restart
		list_id	Numeric value	List ID acquired by
				/cgi-bin/get_mp4_list2


Usage example) Select 000120150101

http://192.168.0.10/cgi-bin/set_playscene_mp4?filename=S0MA001000000110&list_id=123

Usage example) Start playback of the selected file http://192.168.0.10/cgi-bin/playcmd_mp4?type=start&list_id=123

- * If you perform playback during the use of the SD card, "ErrorNo=3" is returned in the main text. You cannot perform playback in such a case.
- * The playback video is converted to JPEG format and transmitted. Use /cgi-bin/view_pb.cgi for acquisition of video.

8.8. MP4 File Playback Sequence



8.9. MP4 File Deletion

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Deletion of stored	/cgi-bin/del_mp4	fileno	Numeric value	File No. acquired by
data	_file			/cgi-bin/get_mp4_list2
				* A max. of up to 50 files can be
				specified.
		list_id	Numeric value	List ID acquired by
				/cgi-bin/get_mp4_list2

Usage example) Delete file no. 1 and 2 http://192.168.0.10/cgi-bin/del_mp4_file?fileno=1,2&list_id=123

8.10. Acquiring Information of MP4 File being Played Back

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Playback data information acquisition	/cgi-bin/get_play sceneinfo	type	playscene setscene	playscene: Information about content being played back setscene: Information about set content
				* Can be omitted • If the "type" has not been specified, assume type = playscene.
				If this CGI is not called once in 30 seconds during playback, the playback process will stop.

The response data is as shown below.

playtype = play/stop/pause

filename = String

startpts = Numeric value

endpts = Numeric value

curtime = Numeric value (time period [msec] from start)

duration = hh:mm:ss

time = mm/dd/yyyy hh:mm:ss

sdrec_mode = String (same as "value" of /cgi-bin/set_sdrec_mode)

8.11. MP4 File Download Control


Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Download through file specification	/cgi-bin/get_mp4 _file	filename	String	File name acquired by /cgi-bin/get_mp4_list2
		list_id	Numeric value	List ID acquired by /cgi-bin/get_mp4_list2

Usage example) Download the file 000120150101.

http://192.168.0.10/cgi-bin/get_mp4_file?filename=S0MA00100000110&list_id=123

8.12. MP4 File Download Sequence



During download, the remote camera issues a response by assuming the file name acquired by /cgi-bin/get_mp4_list2 (ex. S0MA001000000110.mp4) as the default file name. After completion of download, it is recommended to rename to the date acquired by /cgi-bin/get_mp4_list2.

8.13. Still picture image save

** Both HE 40 / UE 70 series require Ver. 1.8 or later.

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Still picture image	/cgi-bin/image	action	save	save: Still picture image save
Control		fileno	Numeric value	Action target still picture image file number. XX of "S10000XX.JPG"(1~99)
		output	off	Still picture image data response
			on	after save
				(Optional, off by default)

Usage example) Save to S1000001.JPG file http://192.168.0.10/cgi-bin/image?action=save&fileno=1

The response data is as shown below.

"Image Save OK"	Still picture image save is success (output = off)
···(JPEG)···	Still picture image save is success (output = on)
"Image Bad Request"	Bad Request
"Image Internal Server Error"	Standby state or JPEG transfer disabled state
"Check Media"	Media factor error (no card, card error)
"Media Busy"	Status error (Can not operate due to media access etc.)
"Image Save Error"	Other error

The resolution / picture quality of the still picture to be saved conforms to the setting contents of JPEG (1) of WEB menu / Video over IP / JPEG. When JPEG (1) is off, it conforms to the setting contents of JPEG (2) or JPEG (3).

The recording destinations inside the SD card are as follows.

PRIVATE/100CDPFQ/S10000XX.JPG

XX= fileno

The saved still picture image is not transferred by the FTP transfer function of chapter 7.

8.14. Still picture image load / delete / find

** Both HE 40 / UE 70 series require Ver. 1.8 or later.

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Still picture image	/cgi-bin/image	action	load	load: Still picture image load
Control			delete	delete: Still picture image delete
			find	find: Still picture image find
		fileno	Numeric value	Action target still picture image file
				number.
				XX of "S10000XX.JPG"(1~99)

Usage example) load S1000001.JPG file

http://192.168.0.10/cgi-bin/image?action=load&fileno=1

The response data is as shown below.

···(JPEG)···	Still picture image load is success
"Image Find NG"	The file with the specified number does not exist
"Image Load Error"	Other error

Usage example) delete S1000001.JPG file

http://192.168.0.10/cgi-bin/image?action=delete&fileno=1

The response data is as shown below.

"Image Delete OK"	Still picture image delete is success
"Image Find NG"	The file with the specified number does not exist
"Image Delete Error"	Other error

Usage example) find S1000001.JPG file

http://192.168.0.10/cgi-bin/image?action=find&fileno=1

The response data is as shown below.

"Image Find OK"	The file with the specified number exists
"Image Find NG"	The file with the specified number does not exist

The Common error response data is as shown below.

"Image Bad Request"	Bad Request
"Image Internal Server Error"	Standby state or JPEG transfer disabled state
"Check Media"	Media factor error (no card, card error)
"Media Busy"	Status error (Can not operate due to media access etc.)

9. Acquiring the List of Setting Values

Method : GET Access level : Live

CGI item name	URL	Parameter name	Parameter value	Description
Acquisition of list of	/cgi-bin/setdata			Parameters are not required.
setting values				

The response data is as shown below.

CAMTITLE,"AW-HE70"

IMAGESELECT,"2m"

IMAGERATIO, "16_9"

IMAGEFPS,"30"

LIVESTREAM,"h264_4"

LIVEINT,"30"

LIVEQUALBASE,"1"

LIVESIZE,"640"

LIVEQUAL,"5"

LIVESIZE2,"1280"

LIVEQUAL2,"5"

LIVESIZE3,"320"

LIVEQUAL3,"5"

STREAMMODE,"1"

H264,"1"

H264RTSPMODE,"0"

H264BWC, "8192"

NRH264BWC,"1024"

H264BWCMIN,"6144"

H264SIZE,"1280"

NRH264SIZE,"1280"

H264FPRIORITY,"2"

H264NRFRAMERATE, "30"

H264QUAL, "fine"

NRH264QUAL,"normal"

H264RINT,"1"

H264MTD,"multi"

H264MLADD1,"239"

H264MLADD2,"192"

H264MLADD3,"0"

H264MLADD4,"20"

H264MLADD, "239.192.0.20"

H264MLPORT, "37004"

H264MLTTL,"16"

H264UNIPORT, "32004"

H264UNIPORT2,"33004"

H264PROFILE,"0"

H264_2,"1"

H264RTSPMODE_2,"0"

H264BWC 2,"8192"

NRH264BWC 2,"1024"

H264BWCMIN 2,"4096"

H264SIZE 2,"1280"

NRH264SIZE 2,"640"

H264FPRIORITY_2,"1"

H264NRFRAMERATE 2,"30"

H264QUAL_2,"low"

NRH264QUAL_2,"normal"

H264RINT_2,"1"

H264MTD_2,"uni"

H264MLADD1_2,"239"

H264MLADD2_2,"192"

H264MLADD3_2,"0"

H264MLADD4_2,"21"

H264MLADD 2,"239.192.0.21"

H264MLPORT_2,"37004"

H264MLTTL_2,"16"

H264UNIPORT 2,"32014"

H264UNIPORT2 2,"33014"

H264PROFILE_2,"0"

H264_3,"1"

H264RTSPMODE_3,"0"

H264BWC_3,"4096"

NRH264BWC_3,"1024"

H264BWCMIN_3,"1024"

H264SIZE_3,"640"

NRH264SIZE_3,"640"

H264FPRIORITY_3,"1"

H264NRFRAMERATE_3,"30"

H264QUAL_3,"low"

NRH264QUAL_3,"normal"

H264RINT 3,"1"

H264MTD_3,"uni"

H264MLADD1_3,"-"

H264MLADD2_3,"-"

H264MLADD3_3,"-" H264MLADD4_3,"-"

H264MLADD 3,"ff02::1"

H264MLPORT_3,"37004"

H264MLTTL_3,"16"

H264UNIPORT 3,"32024"

H264UNIPORT2_3,"33024"

H264PROFILE 3,"0"

H264_4,"1"

H264RTSPMODE_4,"1"

H264BWC_4,"1536"

NRH264BWC_4,"1024"

H264BWCMIN 4,"512"

H264SIZE_4,"320"

NRH264SIZE 4,"640"

H264FPRIORITY 4,"0"

H264NRFRAMERATE_4,"30"

H264QUAL_4,"low"

NRH264QUAL_4,"normal"

H264RINT_4,"1"

H264MTD_4,"uni"

H264MLADD1_4,"239"

H264MLADD2_4,"192"

H264MLADD3_4,"0"

H264MLADD4_4,"23"

H264MLADD_4,"239.192.0.23"

H264MLPORT_4,"37004"

H264MLTTL_4,"16"

H264UNIPORT_4,"32034"

H264UNIPORT2_4,"33034"

H264PROFILE_4,"0"

RTSPPORT,"554"

H264MLAUTO,"0"

H264MLAUTO_2,"0"

H264MLAUTO_3,"0"

H264MLAUTO_4,"0"

AUDIO,"in"

AUDIOSENS,"line_middle"

AUDIOBITRATE,"128"

AUDIOENC."2"

AUDIOMIC, "internal"

PLUGIN_HALFTONE_JPEG,"0"

PLUGIN HALFTONE H264,"0"

The description of the response data is as shown below.

Setting name	Value	Description
CAMTITLE	String	Camera name
IMAGESELECT	2m	Imaging mode
		2m: 2 M pixel
IMAGERATIO	16_9	Image ratio
		16_9: 16:9 mode
IMAGEFPS	30	Frame rate

Setting name	Value	Description
		30: 30 fps
LIV/COTDE ANA	1.004	Literature Seffel at a consideration
LIVESTREAM	h264	Live screen initial stream selection
	h264_2	h264:H264(1)
	h264_3	h264_2:H264(2)
	h264_4	h264_3:H264(3)
	jpeg	h264_4:H264(4)
	jpeg_2	jpeg:JPEG(1)
	jpeg_3	jpeg_2:JPEG(2)
		jpeg_3:JPEG(3)
LIVEINT	1	JPEG(1) refresh interval
	5	1:1fps
	15(12.5)	5:5fps
	30(25)	15(12.5):15(12.5)fps
		30(25):30(25)fps
		* The values within () are for the case when the
		system frequency is 50 Hz
LIVEQUALBASE	1	JPEG(1) default image quality
		1: Image quality 1
LIVESIZE	320	JPEG(1) image resolution
	640	320:320x180
	1280	640:640x360
	1920	1280:1280x720
		1920:1920x1080
LIVESIZE2	320	JPEG(2) image resolution
	640	320:320x180
	1280	640:640x360
		1280:1280x720
LIVESIZE3	320	JPEG(3) image resolution
	640	320:320x180
	1280	640:640x360
		1280:1280x720
LIVEQUAL	1	JPEG(1) image quality
	5	1: Fine
		5: Normal
LIVEQUAL2	1	JPEG(2) image quality
	5	1: Fine
		5: Normal
LIVEQUAL3	1	JPEG(3) image quality
	5	1: Fine
		5: Normal
STREAMMODE	1	Movie transmission method
OTIVEAMINIODE	'	1: H264
H264	0	H264 transmission ON/OFF
	┥ .	0: OFF
H264_2	<u> </u>	
H264_3		1: ON

Setting name	Value	Description
H264_4		
H264RTSPMODE	0	Internet mode ON/OFF
H264RTSPMODE_2	1	0: OFF
H264RTSPMODE_3		1: ON
H264RTSPMODE_4		
H264BWC	512,768,1024,1536,	Bit rate per client
	2048,3072,4096,6144,	512 (kbps)
H264BWC_2	8192,10240,12288,	~
	14336,16384,20480,	24576 (kbps)
H264BWC_3	24576,	~
	32768(*1),	51200 (kbps)
H264BWC_4	40960(*1),	
	51200(*1)	(*1): Only for UE70 series
H264BWCMIN	512,768,1024,1536,	Minimum bit rate per client
	2048,3072,4096,6144,	512 (kbps)
H264BWCMIN_2	8192,10240,12288,	~
	14336,16384,20480,	24576 (kbps)
H264BWCMIN_3	24576,	~
	32768(*1),	51200 (kbps)
H264BWCMIN_4	40960(*1),	
	51200(*1)	(*1): Only for UE70 series
NRH264BWC	Numeric value	Bit rate per client at which transmission does not
NRH264BWC_2		stop
NRH264BWC_3		Unit [kbps]
NRH264BWC_4		* The value acquired by setdata depends on the
		minimum bit rate per client.
H264SIZE	320	H264(1) resolution
	640	320:320x180
	1280	640:640x360
	1920	1280:1280x720
	3840(*1)	1920:1920x1080
		(*1): Only for UE70 series
H264SIZE_2	320	H264(2) resolution
	640	320:320x180
	1280	640:640x360
		1280:1280x720
H264SIZE_3	320	H264(3) resolution
	640	320:320x180
	1280	640:640x360
		1280:1280x720
H264SIZE_4	320	H264(4) resolution
	640	320:320x180
	1280	640:640x360
		1280:1280x720

Setting name	Value	Description
NRH264SIZE	320	H264(1) resolution at which transmission does not
	640	stop
	1280	320:320x180
	1920	640:640x360
	3840(*1)	1280:1280x720
		1920:1920x1080
		3840: 3840x2160 (*1)
		(*1): Only for UE70 series
		The value acquired by setdata depends on the value
		of H264(1).
NRH264SIZE_2	320	H264(2) resolution at which transmission does not
	640	stop
	1280	320:320x180
		640:640x360
		1280:1280x720
		The value acquired by setdata depends on the value
		of H264(2).
NRH264SIZE_3	320	H264(3) resolution at which transmission does not
	640	stop
	1280	320:320x180
		640:640x360
		1280:1280x720
		The value acquired by setdata depends on the value
		of H264(3).
NRH264SIZE_4	320	H264(4) resolution at which transmission does not
	640	stop
	1280	320:320x180
		640:640x360
		1280:1280x720
		The value acquired by setdata depends on the value
		of H264(4).
H264FPRIORITY	0	Transmission mode
H264FPRIORITY_2	1	0:Constant bit rate
H264FPRIORITY_3	2	1:Frame rate
H264FPRIORITY_4		2:Best effort
H264NRFRAMERATE	5	H264(1) frame rate
	15(12.5)	5:5fps
	30(25)	15(12.5):15(12.5)fps
	60(50)	30(25):30(25)fps
		60(50):60(50)fps
		* The values within () are for the case when the
		system frequency is 50 Hz
H264NRFRAMERATE_	5	H264(2) frame rate
2	15(12.5)	5:5fps
	30(25)	15(12.5):15(12.5)fps
		30(25):30(25)fps
		, , , , , , , ,

*The values within () are for the case when the system frequency is 50 Hz	Setting name	Value	Description
H264NRFRAMERATE_ 5			* The values within () are for the case when the
3			system frequency is 50 Hz
3			
3			
15(12.5):15(12.5)fps 30(25)s0(25)fps	H264NRFRAMERATE_		H264(3) frame rate
30(25):30(25)fps	3	· · · · ·	·
* The values within () are for the case when the system frequency is 50 Hz ### H264NRFRAMERATE_ 4		30(25)	
System frequency is 50 Hz			
H264NRFRAMERATE_			
15(12.5) 5:5fps 30(25) 30(25) 30(25);30(25)fps 30(25);30(25)fps 30(25);30(25)fps 30(25);30(25)fps *The values within () are for the case when the system frequency is 50 Hz H264QUAL		_	
15(12.5):15(12.5)fps 30(25);30(25)fps * The values within () are for the case when the system frequency is 50 Hz H264QUAL fine H264 image quality H264QUAL_3 low: Motion priority H264QUAL_4 NRH264QUAL normal H264 image quality at which transmission does not stop normal: Standard NRH264QUAL_3 normal H264 image quality at which transmission does not stop normal: Standard NRH264QUAL_4 H264RINT 1 Refresh cycle 1: 1 second H264RINT_2 H264RINT_3 H264RINT_4 luni multi unicast port(AUTO) uni_manual: Unicast port(AUTO) uni_manual: Unicast port(MANUAL) multi: Multicast H264MTD_3 multi unicast port(MANUAL) multi: Multicast address First octet 224 to 239 H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(2) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(2) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(2) multicast address First octet 0 to 255			` ` '
30(25):30(25)fps * The values within () are for the case when the system frequency is 50 Hz H264QUAL fine H264 image quality H264QUAL_2 low fine: Image quality priority low: Motion priority H264QUAL_4 NRH264QUAL_2 NRH264QUAL_2 normal H264 image quality at which transmission does not stop NRH264QUAL_2 normal Standard NRH264QUAL_2 normal: Standard NRH264QUAL_3 normal: Standard NRH264QUAL_3 normal: Standard NRH264QUAL_4 H264RINT 1 Refresh cycle 1: 1 second H264RINT_3 H264RINT_3 H264RINT_3 uni H264 transmission method uni-Unicast port(AUTO) uni_manual:Unicast port(MANUAL) multi:Multicast H264MTD_4 uni_manual:Unicast address First octet 224 to 239 H264MLADD1 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(2) multicast address First octet 0 to 255 H264MLADD2 Numeric value H264(2) multicast address First octet 0 to 255 H264MLADD2 Numeric value H264(2) multicast address First octet 0 to 255	4	· · · · ·	I .
*The values within () are for the case when the system frequency is 50 Hz H264QUAL_2 low H264 image quality fine: Image quality priority low: Motion priority low: Motion priority H264QUAL_3 H264QUAL_4 NRH264QUAL_4 NRH264QUAL_2 NRH264QUAL_2 NRH264QUAL_3 NRH264QUAL_3 NRH264QUAL_3 NRH264QUAL_4 H264RINT 1 Refresh cycle 1: 1 second H264RINT_2 H264RINT_3 H264RINT_4 H264MTD uni_manual uni_manual: Unicast port(AUTO) uni_manual: Unicast port(MANUAL) multi:Multicast H264MTD_4 H264MTD_4 H264MTD_1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD1 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 1264MLADD1_2 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD2_2 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address First octet 224 to 239 H264(2) multicast address First octet 224 to 239 H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264ML		30(23)	
system frequency is 50 Hz H264QUAL H264QUAL_2 H264QUAL_3 H264QUAL_4 NRH264QUAL NRH264QUAL NRH264QUAL NRH264QUAL NRH264QUAL NRH264QUAL NRH264QUAL NRH264QUAL NRH264QUAL H264RINT H264RINT H264RINT_3 H264MTD_2 H264MTD_3 H264MTD_4 H264MTD_4 H264MTD_4 H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD2_1 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255			
H264QUAL fine H264 image quality fine: Image quality fine: Image quality priority low: Motion priority H264QUAL_3 H264QUAL_4 NRH264QUAL normal H264 image quality at which transmission does not stop normal: Standard H264QUAL_3 NRH264QUAL_3 NRH264QUAL_4 H264RINT 1 Refresh cycle 1: 1 second H264RINT_3 H264RINT_4 H264RINT_4 H264MTD uni			l
H264QUAL_2 H264QUAL_3 H264QUAL_4 NRH264QUAL NRH264QUAL NRH264QUAL NRH264QUAL_2 NRH264QUAL_3 NRH264QUAL_3 NRH264QUAL_3 NRH264QUAL_3 NRH264QUAL_4 H264RINT 1 1 Refresh cycle 1: 1 second H264RINT_3 H264RINT_4 H264MTD uni uni_manual uni:Unicast port(AUTO) H264MTD_3 multi uni_manual:Unicast port(MANUAL) M264MTD_4 H264MTD_4 H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD3 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD1_2 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264QUAI	fine	
H264QUAL_3	·	┪.	
H264QUAL_4 NRH264QUAL_2 NRH264QUAL_3 NRH264QUAL_4 H264RINT		1	
NRH264QUAL NRH264QUAL_2 NRH264QUAL_3 NRH264QUAL_4 H264RINT 1 Refresh cycle 1: 1 second H264RINT_2 H264RINT_3 H264MTD_1 H264MTD_2 H264MTD_3 H264MTD_4 H264MTD_4 H264MTD_4 H264MLADD1 Numeric value H264MLADD3 Numeric value H264MLADD4 Numeric value H264MLADD4 Numeric value H264MLADD1 H264MLADD2 Numeric value H264MLADD3 Numeric value H264MLADD4 Numeric value H264MLAD4 Numeric value		-	, and the same of
NRH264QUAL_2 stop NRH264QUAL_4 normal: Standard H264RINT 1 H264RINT_2 1: 1 second H264RINT_3 H264RINT_4 H264MTD uni H264MTD_2 uni_manual H264MTD_3 multi H264MTD_4 multi:Multicast port(AUTO) H264MTD_4 multi:Multicast port(MANUAL) H264MTD_4 H264(1) multicast address First octet H264MLADD1 Numeric value H264(1) multicast address First octet 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 <td></td> <td>normal</td> <td>H264 image quality at which transmission does not</td>		normal	H264 image quality at which transmission does not
NRH264QUAL_3 normal: Standard NRH264QUAL_4 H264RINT H264RINT_2 1: 1 second H264RINT_3 H264RINT_4 H264MTD_ uni H264MTD_2 uni_manual H264MTD_3 multi H264MTD_4 multi:Multicast port(MANUAL) H264MTD_4 H264MI uni_manual:Unicast port(MANUAL) H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD2 Numeric value H264(1) multicast address Second octet H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet H264MLADD2_2 Numeric value H264(2) multicast address Second octet H264MLADD2_2 Numeric value H264(2) multicast address Second octet		1	1
NRH264QUAL_4		1	·
H264RINT		-	
H264RINT_2 H264RINT_3 H264RINT_4 H264MTD Uni H264MTD_2 H264MTD_3 H264MTD_4 H264MLADD1 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD1_2 Numeric value H264(2) multicast address First octet 0 to 255		1	Refresh cycle
H264RINT_3 H264RINT_4 H264MTD uni H264 transmission method uni:Unicast port(AUTO) H264MTD_3 multi uni_manual:Unicast port(MANUAL) H264MTD_4 H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255		1	I
H264MTD uni H264MTD_2 uni_manual H264MTD_3 multi H264MTD_4 H264MLADD1 Numeric value H264MLADD3 Numeric value H264MLADD3 Numeric value H264MLADD4 Numeric value H264(1) multicast address First octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255		1	
H264MTD_2 uni_manual uni:Unicast port(AUTO) H264MTD_3 multi uni_manual:Unicast port(MANUAL) H264MTD_4 H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264RINT_4	1	
H264MTD_3 H264MTD_4 H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MTD	uni	H264 transmission method
H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MTD_2	uni_manual	uni:Unicast port(AUTO)
H264MLADD1 Numeric value H264(1) multicast address First octet 224 to 239 H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MTD_3	multi	uni_manual:Unicast port(MANUAL)
H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MTD_4		multi:Multicast
H264MLADD2 Numeric value H264(1) multicast address Second octet 0 to 255 H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MLADD1	Numeric value	H264(1) multicast address First octet
H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255			224 to 239
H264MLADD3 Numeric value H264(1) multicast address Third octet 0 to 255 H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MLADD2	Numeric value	` `
H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255			
H264MLADD4 Numeric value H264(1) multicast address Fourth octet 0 to 255 H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MLADD3	Numeric value	` `
H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255			
H264MLADD1_2 Numeric value H264(2) multicast address First octet 224 to 239 H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MLADD4	Numeric value	` `
H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255			
H264MLADD2_2 Numeric value H264(2) multicast address Second octet 0 to 255	H264MLADD1_2	Numeric value	` ` '
0 to 255	11004141 4550 5	 N	
	H264MLADD2_2	Numeric value	
H264(2) multicast address Third octet	LIOCANAL ADDO. C	Nimerala	
,	H264MLADD3_2	Numeric value	H264(2) multicast address Third octet

Setting name	Value	Description			
		0 to 255			
		Heavier III = II = II			
H264MLADD4_2	Numeric value	H264(2) multicast address Fourth octet			
11004141 ABB4 0	M	0 to 255			
H264MLADD1_3	Numeric value	H264(3) multicast address First octet			
LICCANAL ADDO O	Numeralis	224 to 239			
H264MLADD2_3	Numeric value	H264(3) multicast address Second octet 0 to 255			
HOGAMI ADDO O	Numeric value				
H264MLADD3_3	Numeric value	H264(3) multicast address Third octet 0 to 255			
H264MLADD4_3	Numeric value	H264(3) multicast address Fourth octet			
HZ04WLADD4_3	Numeric value	0 to 255			
H264MLADD1_4	Numeric value	H264(4) multicast address First octet			
TIZOTIVILADDI_T	Numeric value	224 to 239			
H264MLADD2_4	Numeric value	H264(4) multicast address Second octet			
1120 IIII27 (332_1	Trainione raide	0 to 255			
H264MLADD3 4	Numeric value	H264(4) multicast address Third octet			
		0 to 255			
H264MLADD4_4	Numeric value	H264(4) multicast address Fourth octet			
_		0 to 255			
H264MLADD	(IPv4 address)	H264 multicast address			
H264MLADD_2	or				
H264MLADD_3	(IPv6 address)				
H264MLADD_4					
H264MLPORT	Numeric value	H264 multicast port			
H264MLPORT_2		1024 to 50000			
H264MLPORT_3					
H264MLPORT_4					
H264MLTTL	Numeric value	H264 multicast TTL 1 to 254			
H264MLTTL_2					
H264MLTTL_3					
H264MLTTL_4					
H264UNIPORT	Numeric value	H264 unicast (for video) port number			
H264UNIPORT_2		1024 to 50000 (only even numbers)			
H264UNIPORT_3					
H264UNIPORT_4					
H264UNIPORT2	Numeric value	H264 unicast (for audio) port number			
H264UNIPORT2_2		1024 to 50000 (only even numbers)			
H264UNIPORT2_3					
H264UNIPORT2_4					
H264PROFILE	0	H264 profile			
H264PROFILE_2		0: High profile			
H264PROFILE_3					
H264PROFILE_4					
RTSPPORT	Numeric value	RTSP server port number			

Setting name	Value	Description
H264MLAUTO	0	Multicast delivery is started automatically.
H264MLAUTO_2		0: OFF
H264MLAUTO 3		
H264MLAUTO 4		
AUDIO	in	Audio settings
	off	in: ON
		off: OFF
AUDIOSENS	low	Sound collection sensitivity
	middle	low: Mic Low
	high	middle: Mic Middle
	line_low	high: Mic High
	line_middle	line_low: Line Low
	line_high	line_middle: Line Middle
		line_high: Line High
AUDIOBITRATE	64	Audio bit rate
	96	64: 64 Kbps
	128	96: 96 Kbps
		128: 128 Kbps
AUDIOENC	2	Encoder settings
		2: AAC
PLUGIN_HALFTONE_J	0	Enabling/disabling of half-tone function for JPEG
PEG		images in Active X
		0: Disabled
PLUGIN_HALFTONE_	0	Enabling/disabling of half-tone function for H264 in
H264		Active X
		0: Disabled

10. About Control Based on RTSP

The remote camera supports general RTSP protocols as well. This chapter illustrates usage methods based on RTSP. The customer must have knowledge of RTSP/RTP/RTCP when using such usage methods.

10.1. About the URLs for an RTSP Request

The URLs for RTSP requests of the remote camera are as described below.

Request URL	Description	
rtsp:// <cam_ip>/mediainput/h264/stream_1</cam_ip>	Videos set in WEB menu H264(1) of the remote	
rtsp:// <cam_ip>/inediainpu/ii264/stream_i</cam_ip>	camera can be requested.	
rtsp:// <cam_ip>/mediainput/h264/stream_2</cam_ip>	Videos set in WEB menu H264(2) of the remote	
rtsp:// <cam_ip>/mediainpu/nz64/stream_z</cam_ip>	camera can be requested.	
stand sam in /madiainnut/h264/atraam 2	Videos set in WEB menu H264(3) of the remote	
rtsp:// <cam_ip>/mediainput/h264/stream_3</cam_ip>	camera can be requested.	
standle com in Imadiainnut/h264/atroom 4	Videos set in WEB menu H264(4) of the remote	
rtsp:// <cam_ip>/mediainput/h264/stream_4</cam_ip>	camera can be requested.	

The RTSP port at the remote camera (RTSP Server) side is set to 554 according to the factory settings. If it is to be changed, use the cgi-bin/set_rtsp (POST command).

The relationship between "H.264 transmission" and "Audio Transmission" in the WEB menu of the remote camera is as shown below.

		Audio Transmission				
		ON	OFF			
H.264 transmission	ON	Both video and audio can be used. * As for DESCRIBE, the SDP information of video + audio is issued as response.	Only video can be used. * As for DESCRIBE, only the SDP information of video is issued as response.			
transmission	OFF	Both video and audio cannot be used. * As for SETUP, 503 is issued as respo	nse.			

When "Audio Transmission" is ON, the remote camera issues a response by adding Audio information to the DESCRIBE information. If necessary, the audio can be transmitted by issuing the SETUP command. On the contrary, if the SETUP command is not issued, only the video can be transmitted. Moreover, if "Audio" in the WEB menu of the remote camera is "OFF", or nothing is connected to the "Audio IN terminal", it results in silent transmission.

In this manual, the description is provided by assuming that "H.264 transmission" and "Audio Transmission" are in the ON state.

10.2. About the rtsp Methods

The RTSP methods supported in the remote camera are as described below.

Supported Method	Description
OPTIONS	Check for the corresponding command
DESCRIBE	Acquisition of session information and Audio support
SETUP	Initialization of the session and mutual exchange of
SETUP	port information
PLAY	Transfer started
	Transfer paused
PAUSE	* Transmission is stopped, and this method is
	ignored during multicast.
GET PARAMETER	Acquisition of session parameter
GEI_PARAWETER	* Operation is performed by assuming Keep Alive.
TEARDOWN	Transfer end/session end

SET_PARAMETER is not supported. 501 is issued as response.

The timeout based on GET_PARAMETER is 120 seconds. If Keep Alive from all clients is blocked including during multicast, the remote camera stops transmission.

11. About Acquisition of Stream from RTSP

The RTSP communication methods supported in the remote camera are as described below. No matter which method is used, TCP communication (554 is set as the waiting port at the remote camera side) is used during initial negotiation of RTSP.

1. UDP Unicast

- Used for transmitting video/audio to a single client in one remote camera.
- Although transmission to multiple clients is also supported, network bandwidth is needed for each connection.

2. UDP Multicast

- Used for transmitting video/audio simultaneously to multiple clients in one remote camera.
- The network bandwidth at the camera side does not increase even when transmission is performed to multiple clients.
- A separate router that supports multicast is needed.

3. TCP Unicast

- Used for transmitting video/audio to a single client in one remote camera.
- The video and audio data communicated via RTP/UDP can be transmitted via TCP.

11.1. UDP Unicast

You must make the settings described below in the WEB menu as preparations at the remote camera side.

■ Set H264(X)/Transmission type to Unicast (AUTO).

The port number during transmission of video and audio stream is decided as described below.

• client_port (receiving port at the client side):

The client explicitly issues a command to the remote camera in an RTSP "SETUP" sequence.

- * The methods of deciding the port number differ according to the client, and include random settings and dedicated menu.
- server_port (transmitting port of the remote camera):


The remote camera issues a response to the client through response in the RTSP "SETUP" sequence.

* The port number is decided randomly.

Note that if you want to fix the client_port forcibly, you can do so by making the WEB menu settings described below.

- Set H264(X)/Transmission type to Unicast (MANUAL).
- Set Unicast port (Image)/Unicast port (Audio).
- * However, in the RTSP "SETUP" sequence, the content instructed explicitly by the client to the remote camera are ignored, and therefore, it is not used normally.

The acquisition method of video and audio stream by the UDP Unicast method is illustrated below.



```
OPTIONS rtsp://<cam_ip>/mediainput/h264/stream_1 RTSP/1.0
CSeq: 2
User-Agent: <User-Agent>
RTSP/1.0 200 OK
CSeq: 2
Public: OPTIONS, DESCRIBE, SETUP, PLAY, PAUSE, GET PARAMETER, TEARDOWN
DESCRIBE rtsp://<cam_ip>/mediainput/h264/stream_1 RTSP/1.0
User-Agent: <User-Agent>
RTSP/1.0 200 OK
CSeq: 3
Content-Base: rtsp://<cam_ip>/mediainput/h264/stream_1/
Content-Type: application/sdp
Content-Length: <Length>
v=0
o=- 1 1 IN IP4 <cam_ip>
s=Media Presentation
e=NONE
c=IN IP4 0.0.0.0
b=AS:14464
t=0 0
a=control:*
a=range:npt=now-
m=video 0 RTP/AVP 98
b=AS:14336
a=framerate:30.0
a=control:trackID=1
a=rtpmap:98 H264/90000
a=fmtp:98 packetization-mode=1
a=h264-esid:201
m=audio 0 RTP/AVP 99
a=control:trackID=2
a=rtpmap:99 mpeg4-generic/48000/2
a=fmtp:99 streamType=5; profile-level-id=41; mode=AAC-hbr; config=1190; sizeLength=13; indexLength=3;
indexDeltaLength=3; bitrate=128000
a=h264-esid:101
SETUP rtsp://<cam ip>/mediainput/h264/stream 1/trackID=1RTSP/1.0
CSeq: 4
User-Agent: <User-Agent>
Transport: RTP/AVP;unicast;client port=<CliUdpPortV>-<CliUdpPortV+1>
RTSP/1.0 200 OK
CSeq: 4
Session: <SessionId>;timeout=120
Transport: RTP/AVP/UDP;unicast;client port=<CliUdpPortV>-<CliUdpPortV+1>;
                             server port=<SrvUdpPortV>-<SrvUdpPortV+1>;ssrc=<SSRC>
```

UDP Unicast Packets (1/2)

```
SETUP rtsp://<cam_ip>/mediainput/h264/stream_1/trackID=2 RTSP/1.0
CSeq: 5
User-Agent: <User-Agent>
Transport: RTP/AVP;unicast;client_port=<CliUdpPortA>-<CliUdpPortA+1>
Session: <SessionId>
RTSP/1.0 200 OK
CSeq: 5
Session: <SessionId>;timeout=120
Transport: RTP/AVP/UDP; unicast; client port=<CliUdpPortA>-<CliUdpPortA+1>;
                              server_port=<SrvUdpPortA>-<SrvUdpPortA+1>;ssrc=<SSRC>
PLAY rtsp://<cam_ip>/mediainput/h264/stream_1/ RTSP/1.0
CSeq: 6
User-Agent: <User-Agent>
Session: <SessionId>
Range: npt=0.000-
RTSP/1.0 200 OK
CSeq: 6
Session: <SessionId>
RTP-Info: url=trackID=1;seq=<SequenceNumber>;rtptime=...
         url=trackID=2;seq=<SequenceNumber>;rtptime=...
<VIDEO Stream in RTP payload over UDP>
<AUDIO Stream in RTP payload over UDP>
GET PARAMETER rtsp://<cam ip>/mediainput/h264/stream 1/RTSP/1.0
CSeq: 7
User-Agent: <User-Agent>
Session: <SessionId>
RTSP/1.0 200 OK
CSeq: 7
Session: <SessionId>
TEARDOWN rtsp://<cam ip>/mediainput/h264/stream 1/RTSP/1.0
User-Agent: <User-Agent>
Session: <SessionId>
RTSP/1.0 200 OK
CSeq: 8
Session: <SessionId>
```

UDP Unicast Packets (2/2)


11.2. UDP Multicast

You must make the settings described below in the WEB menu as preparations at the remote camera side.

- Set H264(X)/Transmission type to Multicast.
- Set H264(X)/Multicast address (set to 239.192.0.20 for H264(1) according to factory settings)
- Set H264(X)/Multicast port (set to 37004 for H264(1) according to factory settings)

The port number and multicast address during transmission of the video and audio stream depend on the values of the WEB menu of the remote camera, and the commands from the client side are ignored.

The acquisition method of video and audio stream by the UDP Multicast method is illustrated below.



```
OPTIONS rtsp://<cam_ip>/mediainput/h264/stream_1 RTSP/1.0
CSeq: 2
User-Agent: <User-Agent>
RTSP/1.0 200 OK
CSeq: 2
Public: OPTIONS, DESCRIBE, SETUP, PLAY, PAUSE, GET_PARAMETER, TEARDOWN
DESCRIBE rtsp://<cam ip>/mediainput/h264/stream 1 RTSP/1.0
CSeq: 3
User-Agent: <User-Agent>
RTSP/1.0 200 OK
CSeq: 3
Content-Base: rtsp://<cam_ip>/mediainput/h264/stream_1/
Content-Type: application/sdp
Content-Length: <Length>
v=0
o=- 1 1 IN IP4 <cam ip>
s=Media Presentation
e=NONE
c=IN IP4 0.0.0.0
b=AS:14464
t=0 0
a=control:*
a=range:npt=now-
m=video 0 RTP/AVP 98
b=AS:14336
a=framerate:30.0
a=control:trackID=1
a=rtpmap:98 H264/90000
a=fmtp:98 packetization-mode=1
a=h264-esid:201
m=audio 0 RTP/AVP 99
a=control:trackID=2
a=rtpmap:99 mpeg4-generic/48000/2
a=fmtp:99 streamType=5; profile-level-id=41; mode=AAC-hbr; config=1190; sizeLength=13; indexLength=3;
indexDeltaLength=3; bitrate=128000
a=h264-esid:101
SETUP rtsp://<cam ip>/mediainput/h264/stream 1/trackID=1RTSP/1.0
CSeq: 4
User-Agent: <User-Agent>
Transport: RTP/AVP; multicast; client port=52944-52945
RTSP/1.0 200 OK
CSeq: 4
Session: <SessionId>;timeout=120
Transport: RTP/AVP/UDP; multicast; destination =< M ip>;
ttl=16;port=<Mport>-<Mport+1>
```

UDP Multicast Packets (1/2)

```
SETUP rtsp://<cam_ip>/mediainput/h264/stream_1/trackID=2RTSP/1.0
CSeq: 5
User-Agent: <User-Agent>
Transport: RTP/AVP;multicast;client_port=52946-52947
Session: <SessionId>
RTSP/1.0 200 OK
CSeq: 5
Session: <SessionId>;timeout=120
Transport: RTP/AVP/UDP; multicast; destination = < M ip>;
ttl=16;port=<Mport+1000>-<Mport+1001>
PLAY rtsp://<cam_ip>/mediainput/h264/stream_1/RTSP/1.0
CSeq: 6
User-Agent: <User-Agent>
Session: <SessionId>
Range: npt=0.000-
RTSP/1.0 200 OK
CSeq: 6
Session: <SessionId>
RTP-Info: url=trackID=1;seq=<SequenceNumber>;rtptime=...
         url=trackID=2;seq=<SequenceNumber>;rtptime=...
GET_PARAMETER rtsp://<cam_ip>/mediainput/h264/stream_1/RTSP/1.0
CSeq: 7
User-Agent: <User-Agent>
Session: <SessionId>
RTSP/1.0 200 OK
CSeq: 7
Session: <SessionId>
```

UDP Multicast Packets (2/2)

11.3. TCP Unicast

You must make the settings described below in the WEB menu as preparations at the remote camera side.


Set H264(X)/Transmission type to Unicast (AUTO).

The port number during transmission of video and audio stream is decided as described below.

- client_port (receiving port at the client side):
 The transmission-side port of the client that is used in the RTSP "PLAY" sequence becomes the receiving port at the client side.
 - * The methods of deciding the port number differ according to the client, and include random settings and dedicated menu.
- server_port (transmitting port of the remote camera):
 The RTSP waiting port (set to 554 according to factory settings) is used.

The interleave header specified from the client side is ignored at the camera side, and a new interleave header is issued.

The acquisition method of video and audio stream by the TCP Unicast method is illustrated below.



```
OPTIONS rtsp://<cam_ip>/mediainput/h264/stream_1 RTSP/1.0
CSeq: 2
User-Agent: <User-Agent>
RTSP/1.0 200 OK
CSeq: 2
Public: OPTIONS, DESCRIBE, SETUP, PLAY, PAUSE, GET PARAMETER, TEARDOWN
DESCRIBE rtsp://<cam_ip>/mediainput/h264/stream_1 RTSP/1.0
User-Agent: <User-Agent>
Accept: application/sdp
RTSP/1.0 200 OK
CSeq: 3
Content-Base: rtsp://<cam_ip>/mediainput/h264/stream_1/
Content-Type: application/sdp
Content-Length: <Length>
v=0
o=- 1 1 IN IP4 <cam ip>
s=Media Presentation
e=NONE
c=IN IP4 0.0.0.0
b=AS:14464
t=00
a=control:*
a=range:npt=now-
m=video 0 RTP/AVP 98
b=AS:14336
a=framerate:30.0
a=control:trackID=1
a=rtpmap:98 H264/90000
a=fmtp:98 packetization-mode=1
a=h264-esid:201
m=audio 0 RTP/AVP 99
a=control:trackID=2
a=rtpmap:99 mpeg4-generic/48000/2
a=fmtp:99 streamType=5; profile-level-id=41; mode=AAC-hbr; config=1190; sizeLength=13;
indexLength=3; indexDeltaLength=3; bitrate=128000
a=h264-esid:101
SETUP rtsp://<cam ip>/mediainput/h264/stream 1/trackID=1RTSP/1.0
CSeq: 4
User-Agent: <User-Agent>
Transport: RTP/AVP/TCP; unicast; interleaved=0-1
RTSP/1.0 200 OK
CSeq: 4
Session: <SessionId>;timeout=120
Transport: RTP/AVP/TCP; unicast; interleaved = 20-21; ssrc = < SSRC >
```

TCP Unicast Packets 1/2

```
SETUP rtsp://<cam_ip>/mediainput/h264/stream_1/trackID=2 RTSP/1.0
CSeq: 5
User-Agent: <User-Agent>
Transport: RTP/AVP/TCP;unicast;interleaved=2-3
Session: <SessionId>
RTSP/1.0 200 OK
CSeq: 5
Session: <SessionId>;timeout=120
Transport: RTP/AVP/TCP;unicast;interleaved=22-23;ssrc=<SSRC>
PLAY rtsp://<cam_ip>/mediainput/h264/stream_1/ RTSP/1.0
CSeq: 6
User-Agent: <User-Agent>
Session: <SessionId>
Range: npt=0.000-
RTSP/1.0 200 OK
CSeq: 6
Session: <SessionId>
RTP-Info: url=trackID=1;seq=<SequenceNumber>;rtptime=...
         url=trackID=2;seq=<SequenceNumber>;rtptime=...
GET_PARAMETER rtsp://<cam_ip>/mediainput/h264/stream_1/RTSP/1.0
User-Agent: <User-Agent>
Session: <SessionId>
RTSP/1.0 200 OK
CSeq: 7
Session: <SessionId>
```

TCP Unicast Packets 2/2

11.4 About the rtpmap Attribute

The response of "rtpmap" with respect to the RTSP "DESCRIBE" request is as described below.

Codec	rtpmap Attribute Value				
H.264	a=rtpmap:98 H264/90000				
AAC	a=rtpmap:99 mpeg4-generic/48000/2				

The values described above are used for both video and audio regardless of the bit rate.


12. About Control Based on RTCP

The remote camera also supports dynamic control of bit rate and frame rate according to the line status using RTCP. As a prerequisite, a client that supports RTCP/SR (Sender Report) and RTCP/RR (Receiver Report) is necessary.

You must make the settings described below in the WEB menu as preparations at the remote camera side.

- Set H264(X)/Transmission priority to Best effort.
 - * In the case of the frame rate (factory settings) and constant bit rate, an RTCP/SR is transmitted and an RTCP/RR is received, but these are not used for controlling the bit rate and frame rate.
- Select H264(X)/Image quality from Motion priority or Image quality priority.
 Motion priority: This is the motion priority mode. The bit rate is actively changed and supported.
 Image quality priority: This is the image quality priority mode. The frame rate is actively changed.

The sequence during RTCP control is illustrated below:



Note that in the remote camera, an RTCP/SR is transmitted every five seconds, and of the RTCP/RRs, only those related to VIDEO are used.

13. About RTP/Data Format


13.1. RTP Header Format

Bit	0.	0.		8.		16.	24.	
Byte	2	1	1	4	1	7	8	8
0	٧	Р	Χ	CC	М	PT	Sequence	e number
4		Timestamp						
8		SSRC (Synchronization Source Identifier)						
12		Defined by profile Extension length						on length
16		Additional Information (1)						
		Additional Information (N)						

Parameter name	length(Bit)	Values and comments
V (Version)	2	2 (fixed)
P (Padding)	1	0 (fixed)
X (Extension)	1	0: false , 1: true
CC (CSRC Count)	4	0 (fixed)
M (Marker)	1	In case of the last RTP packet of a picture, this value is set to 1
PT (Payload Type)	7	98 (fixed for H.264)
F1 (Fayload Type)	1	99 (fixed for AAC)
Sequence number	16	The value in which one increment is done in each RTP packet is set.
Sequence number		An initial value is generated at random.
Timestamp	32	Time stamp
SSRC	32	0x0000 0000 (fixed)
CSRC	0	Unused
Defined by profile(*)	16	0 (fixed)
Extension length(*)	16	Length of the Header Extension (Unit of 32bit word)
meta information		
(Additional		
Information) (*)		

13.2. Relationship with H.264/ES Data

The structure of ES data and RTP packet of H.264 is as shown below.



103

13.3. H.264 Syntax

In the remote camera, the Codec information to be used changes depending on the resolution/frame rate. The following information is used when Priority Mode is IP or IP (4K) and 59.94 Hz is set, it is as follows.

Resolution / Frame rate	Codec Info		
320x180/5p,15p,30p	H.264/High profile (no B frame/CAVLC)		
640x360/5p,15p,30p	GOP interval approx 1 sec.		
1280x720/5p,15p,30p,60p			
1920x1080/5p,15p,30p			
1920x1080/60p	H.264/High profile (no B frame/CABAC)		
	GOP interval approx 1 sec.		
3840x2160/5p,15p(*1)	H.264/High profile (no B frame/CABAC)		
	GOP interval approx 0.5 sec.		
3840x2160/30p(*1)	H.264/High profile (B frame present/CABAC)		
	GOP interval approx 0.5 sec.		

(*1): Only for UE70 series

13.4. Audio Data Format

The structure of the audio ES data and RTP packet differs depending on the audio compression method.

When the audio compression method is AAC:

An AU header (2 bytes) is inserted between the RTP header and audio data, and then transmitted.



Memo:		